







THE SEWING BOOK



CLOTHES • HOME ACCESSORIES • BEST TOOLS
STEP-BY-STEP TECHNIQUES • CREATIVE PROJECTS

ALISON SMITH

THE SEWING BOOK



THE SEWING BOOK

ALISON SMITH





London, New York, Melbourne,
Munich, and Delhi

PROJECT EDITOR

Norma MacMillan

PROJECT DESIGNERS

Viv Brar
Nicola Collings
Mandy Earey
Heather McCarry

PHOTOGRAPHY

Peter Anderson (Tools and Techniques)
Kate Whitaker (Projects)

For Dorling Kindersley

PROJECT EDITOR Ariane Durkin
PROJECT ART EDITOR Caroline de Souza
MANAGING EDITOR Dawn Henderson
MANAGING ART EDITOR Christine Keilty
SENIOR JACKET CREATIVE Nicola Powling
SENIOR PRODUCTION EDITOR Jenny Woodcock
SENIOR PRODUCTION CONTROLLER Mandy Inness
CREATIVE TECHNICAL SUPPORT Sonia Charbonnier

First American Edition, 2009

Published in the United States by
DK Publishing
375 Hudson Street
New York, New York 10014

09 10 11 12 10 9 8 7 6 5 4 3 2 1

SD397—04/09

Copyright © 2009 Dorling Kindersley Limited
All rights reserved

Without limiting the rights under copyright reserved above, no part of this publication may be reproduced, stored in or introduced into a retrieval system, or transmitted, in any form, or by any means (electronic, mechanical, photocopying, recording, or otherwise), without the prior written permission of both the copyright owner and the above publisher of this book.

Published in Great Britain by Dorling Kindersley Limited.

A catalog record for this book is
available from the Library of Congress.


ISBN 978-0-7566-4280-8

DK books are available at special discounts when purchased in bulk for sales promotions, premiums, fund-raising, or educational use. For details, contact: DK Publishing Special Markets, 375 Hudson Street, New York, New York 10014 or SpecialSales@dk.com.

Color reproduction by MDP, UK

Printed and bound in China by L.Rex Printing Co. Ltd

Discover more at
www.dk.com





CONTENTS

Introduction 6

TOOLS 10

Sewing equipment 12

Fabrics 38

Patterns 56

TECHNIQUES 84

Stitch essentials 86

Darts, tucks, pleats, and gathers 104

Facings and necklines 142

Collars 158

Waistlines, belts, and tie-backs 168

Sleeves and sleeve finishes 188

Pockets 210

Hems and edges 226

Fasteners 248

Linings and interfacings 274

Professional techniques 280



Mending 296

PROJECTS 304

Directory of fashion and soft furnishings 384

Glossary 390

Index, Acknowledgments, and Useful websites 394





INTRODUCTION

The Sewing Book provides a comprehensive guide to all sewing techniques, whether it be for dressmaking, tailoring, crafts, or soft furnishings. If you are new to sewing, you'll find many tips to help and guide you; if you have been sewing for many years, there will be lots of new ideas to try. I also hope the book will be a valuable reference for all students studying textiles and fashion.

Having sewn since my teenage years and taught dressmaking and fashion for all my adult life, I am truly passionate about sewing. It can be so therapeutic—relaxing and satisfying. The ability to produce a unique item of clothing or something for your home is truly rewarding.

The book is divided into three sections. The first, *Tools*, covers all the equipment required to sew, including sewing machines; gives an up-to-date guide to fabrics—their properties, care, and how to sew them; and explains how to alter patterns to make clothes that fit you perfectly.

The next section is *Techniques*, with over 300 different sewing techniques to try, all in a step-by-step photographic format, covering everything from basic stitches and seams through to professional tailoring techniques. Each chapter begins with a visual directory of what the techniques are used for, be it types of pleats or pockets, necklines or sleeves, or buttonhole shapes.

The third section of the book is *Projects*, where you will find 18 items to make, ranging from quick and easy hats through to Roman blinds and kimonos. All the projects use techniques that appear in the second section of the book.

The final section includes an illustrated directory of fashion and home furnishing styles, as well as a useful glossary of sewing terms.

Enjoy and happy sewing.


Alison Smith



ABOUT THIS BOOK

For the photographs, we have often used sewing threads of a contrast color in order for the stitching to be visible. I recommend that you sew with a thread that matches your fabric as closely as possible.

All of the techniques and projects are graded according to difficulty, from * (simple and straightforward) to ***** (more complex and challenging).



Always cut fabric on the straight grain unless the text instructs otherwise.

Seam allowances throughout are $\frac{5}{8}$ in (1.5 cm) unless otherwise indicated.

On many of the fabric samples in the photographs, neatening of the seams is not shown because this can distract from the technique (seam neatening is only shown when it forms part of the technique). I recommend that you neaten your seams using your preferred technique.

Many of the techniques may vary from those given on your paper pattern, but you might like to try an alternative technique. There are many to choose from.



TOOLS





SEWING EQUIPMENT

The minimum equipment for any sewer is a tape measure, at least two pairs of scissors—one pair for cutting fabric and the other for trimming fabrics and threads—pins and needles, possibly a thimble, threads for sewing, a seam ripper, and a container to hold everything. An iron and ironing board will also be needed. There are, however, many other handy gadgets that are invaluable, and for the more enthusiastic sewer, a sewing machine and possibly a serger are essential. Whether you are a beginner to sewing or a sewer with many years of experience, some of the following pieces of equipment will no doubt find their way into your work box.

BASIC SEWING KIT

A well-equipped sewing kit will include all of the items shown below and many more, depending on the type of sewing that you do regularly. It is important that a suitable container is used to keep your tools together, so that they will be readily at hand, and to keep them organized.

THIMBLE

This is useful to protect the end of your finger when hand sewing. Thimbles are available in various shapes and sizes.

See page 21.

TAPE MEASURE

Essential, not only to take body measurements, but also to help measure fabric, seams, etc. Choose one that gives both imperial and metric. A tape made of plastic is best as it will not stretch. See page 18.

ZIPPERS

It is always a good idea to keep a couple of zippers in your sewing kit. Black, cream, and navy are the most useful colors. See pages 250–257.

THREADS

A selection of threads for hand sewing and machine/serger sewing in a variety of colors. Some threads are made of polyester, while others are cotton or rayon. See pages 24–25.

HABERDASHERY

All the odds and ends a sewer needs, including everything from buttons and snaps to trims and elastic. A selection of buttons and snaps in your basic kit is useful for a quick repair. See pages 26–27.

PINS

Needed by every sewer to hold the fabric together prior to sewing it permanently. There are different types of pins for different types of work.

See page 23.

SAFETY PINS

In a variety of sizes and useful for emergency repairs as well as threading elastics. See page 23.



EMBROIDERY SCISSORS

Small pair of scissors with very sharp points, to clip threads close to the fabric. **See page 17.**

NEEDLES

A good selection of different types of needles for sewing by hand. This will enable you to tackle any hand sewing project. **See page 22.**

SEAM RIPPER

Also called a stitch ripper, to remove any stitches that have been sewn in the wrong place. Various sizes of seam rippers are available. Keep the cover on when not in use to protect the sharp point. **See page 16.**

PIN CUSHION

To keep your needles and pins safe and clean. Choose one that has a fabric cover and is firm. **See page 23.**

CUTTING SHEARS

Required for cutting fabric. When buying, select a pair that feels comfortable in your hand and that is not too heavy. **See page 17.**

SEWING GAUGE

A handy gadget for small measurements. The slide can be set to measure hem depths, buttonhole diameters, and much more. **See page 18.**

BUTTONHOLE CHISEL

An exceedingly sharp mini-chisel that gives a clean cut through machine buttonholes. Place a cutting mat underneath when using this tool, or you might damage the blade. **See page 16.**

BUILD UP YOUR SEWING KIT**CUTTING TOOLS 16–17**

BENT-HANDLED SHEARS
CUTTING MAT
PAPER SCISSORS
PINKING SHEARS
ROTARY CUTTER
SNIPS
TRIMMING SCISSORS

MEASURING TOOLS 18

FLEXIBLE RULER
GRIDDED RULER
OTHER TAPE MEASURES

MARKING AIDS 19

CHALK PENCIL
CHALK PROPELLING PENCIL
DRAFTING RULER
TAILOR'S CHALK
TRACING WHEEL AND
CARBON PAPER
WATER/AIR-SOLUBLE PEN

USEFUL EXTRAS 20–21

14-IN-1 MEASURE
AWL
BEESWAX
COLLAR POINT TURNER
DRESSMAKER'S DUMMY
EMERGENCY SEWING KIT
GLUE STICK
LIQUID SEALANT
LOOP TURNER
PATTERN PAPER
PLIERS
BIAS TAPE MAKER
TWEEZERS

NEEDLE THREADERS 22**PRESSING AIDS 28–29**

CLAPPER
IRON
IRONING BOARD
MINI IRON
PRESSING CLOTH
PRESSING MAT
PRESSING MITTEN
SEAM ROLL
TAILOR'S HAM
VELVET MAT

CUTTING TOOLS

There are many types of cutting tools, but one rule applies to all: buy good-quality products that can be re-sharpened. When choosing cutting shears, make sure that they fit the span of your hand—this means that you can comfortably open the whole of the blade with one action, which is very important to allow clean and accurate cutting lines. Shears and scissors of various types are not the only cutting tools that are required, as everyone will at some time need a seam ripper to remove misplaced stitches or to unpick seams for mending. Rotary cutters that are used in conjunction with a special cutting mat and ruler are invaluable for cutting multiple straight edges.



◀ SNIPS

A very useful, small, spring-loaded tool that easily cuts the ends of thread. Not suitable for fabrics.

▼ BUTTONHOLE CHISEL

A smaller version of a carpenter's chisel, to cut cleanly and accurately through buttonholes. As this is so sharp, it must be used with a self-healing cutting mat.



◀ SEAM RIPPER

A sharp, pointed hook to slide under a stitch, with a small cutting blade at the base to cut through the thread. Various sizes of seam ripper are available, to cut through light to heavyweight fabric seams.


▼ ROTARY CUTTER

Available in different sizes of retractable blades. It must be used with a special cutting mat to protect both blade and surface. Used to cut through many layers.



▼ CUTTING MAT

A self-healing mat to use with the rotary cutter. This mat can also be used under the buttonhole chisel.



◀ BENT-HANDLED SHEARS

This type of shear has a blade that can sit flat against the table when cutting out, due to the angle between the blade and handle. Popular for cutting long, straight edges.

PINKING SHEARS ▶

Similar in size to cutting shears, but with a blade that cuts with a zigzag pattern. Used for neatening seams and decorative edges.

▼ CUTTING SHEARS

The most popular type of shear, used for cutting large pieces of fabric. The length of the blade can vary from 8–12 in (20–30 cm).

▲ TRIMMING SCISSORS

These scissors have a 4 in (10 cm) blade and are used to trim away surplus fabric and neaten ends of machining.

▼ EMBROIDERY SCISSORS

A small and very sharp scissor used to get into corners and clip threads close to the fabric.

◀ PAPER SCISSORS

Use these to cut around pattern pieces—cutting paper will dull blades of fabric scissors and shears.

MEASURING TOOLS AND MARKING AIDS

A huge range of tools enables a sewer to measure accurately. Choosing the correct tool for the task at hand is important, so that your measurements are precise. The next step is to mark your work using the appropriate marking technique or tool. Some tools are very specific to one job, while others are specific to types of sewing.

Measuring tools

There are many tools available to help you measure everything from the width of a seam or hem, to body dimensions, to the area of a window. One of the most basic yet invaluable measuring tools is the tape measure. Be sure to keep yours in good condition—once it stretches or gets snipped on the edges, it will no longer be accurate and should be replaced.



METAL TAPE FOR WINDOWS ▲

A metal tape that can be secured when extended is used to measure windows and soft furnishings.




SEWING GAUGE ▲

A handy small tool about 6 in (15 cm) long, marked in inches and centimeters, with a sliding tab. Use as an accurate measure for small measurements such as hems.

RETRACTABLE TAPE ►

Very useful to have in your purse when shopping as you never know when you may need to measure something!




EXTRA-LONG TAPE ▲

This is usually twice the length of a normal tape measure, at 10 ft (300 cm) long. Use it when making soft furnishings. It's also useful to help measure the length of bridal trains.



TAPE MEASURE ▲

Available in various colors and widths. Try to choose one that is the same width as standard seam allowance ($\frac{1}{2}$ in/ 1.5 cm), because it will prove very useful.




FLEXIBLE RULER ▲

A sturdy, flexible piece of plastic, this is perfect to measure armholes or curved shapes. The flexible ruler is also used when altering patterns.

GRIDDED RULER ►

This type of ruler is larger than a normal ruler and is marked with an inch or centimeter grid. Used together with the rotary cutter and mat, and also for marking bias strips.



Marking aids

Marking certain parts of your work is essential, to make sure that things like pockets and darts are placed correctly and seamlines are straight as drawn on the pattern. With some marking tools, such as pens and a tracing wheel and carbon paper, it is always a good idea to test on a scrap of fabric first to make sure that the mark made will not be permanent.

▼ CHALK PROPILING PENCIL

Chalk leads of different colors can be inserted into this propiling pencil, making it a very versatile marking tool. The leads can be sharpened.



◀ WATER/AIR-SOLUBLE PEN

This resembles a felt marker. Marks made can be removed from the fabric with either a spray of water or by leaving to air-dry. Be careful—if you press over the marks, they may become permanent.



TRACING WHEEL AND CARBON PAPER ▶

These two items are used together to transfer markings from a paper pattern or a design on to fabric. Not suitable for all types of fabric though, as marks may not be able to be removed easily.




▲ CHALK PENCIL

Available in blue, pink, and white. As it can be sharpened like a normal pencil, it will draw accurate lines on fabric.

▲ TAILOR'S CHALK

Also known as French chalk, this solid piece of chalk in either a square or triangular shape is available in a large variety of colors. The chalk easily brushes off fabric.



DRAFTING RULER ▲

A plastic curved tool, also called a pattern marking ruler, used primarily when drafting or altering patterns.



USEFUL EXTRAS

There are many more accessories that can be purchased to help with your sewing, and knowing which products to choose and for which job can be daunting. The tools shown here can be useful aids, although it depends on the type of sewing that you do—dressmaking, craft work, making soft furnishings, or running repairs—as to whether you would need all of them in your sewing kit.



◀ BEESWAX

When hand sewing, this will prevent the thread from tangling, and will strengthen it. First draw the thread through the wax, then press the wax into the thread by running your fingers along it.



▲ AWL

This sharp tool is used to make holes in fabric for eyelet insertion or for the rounded end of a keyhole buttonhole.

▼ TWEEZERS

These can be used for removing stubborn basting stitches that have become caught in the machine stitching. An essential aid to threading the serger.



◀ BIAS TAPE MAKER

Available in ½, ¾, and 1 in (12, 18, and 25 mm) widths, this tool evenly folds the edges of a fabric strip, which can then be pressed to make binding.



LOOP TURNER ▶

A thin metal rod with a latch at the end. Use to turn narrow fabric tubes or to thread ribbons through a slotted lace.

▼ EMERGENCY SEWING KIT

All the absolute essentials to fix loose buttons or dropped hems while away from your sewing machine. Take it with you when traveling.




LIQUID SEALANT ▶

Used to seal the cut edge of ribbons and trims to prevent fraying. Also useful to seal the ends of serger stitching.



GLUE STICK ▶

Similar to a glue stick for paper, this will hold fabric or trims temporarily in place until they can be secured with stitches. It will not damage the fabric or make the sewing needle sticky.



**DRESSMAKER'S DUMMY ▲**

An adjustable form that is useful when fitting garments as it can be adjusted to personal body measurements. Excellent to help in the turning up of hemlines. Available in female, male, and children's shapes and sizes.

PATTERN PAPER ►

This can be plain or printed with dots and crosses at regular intervals. The paper can be used for drafting patterns, or for altering or tracing patterns.

COLLAR POINT TURNER ►



This is excellent for pushing out those hard-to-reach corners in collars and cuffs.

**THIMBLE ▼**

An essential item for many sewers, to protect the middle finger from the end of the needle. Choose a thimble that fits your finger comfortably as there are many varieties to choose from.

**▲ PLIERS**

Specially designed pliers with various heads are used to attach grommets, metal snaps, and rivets.

**◀ 14-IN-1 MEASURE**

A strange-looking tool that has 14 different measurements on it. Use to turn hems or edges accurately. Available in both imperial and metric.



NEEDLES AND PINS

Using the correct pin or needle for your work is so important, as the wrong choice can damage fabric or leave small holes. Needles are made from steel and pins from steel or occasionally brass. Take care of them by keeping pins in a pin cushion and needles in a needle case—if kept together in a small container, they could become scratched and blunt.

Needles and threaders

Needles are available for all types of fabrics and projects. A good selection of needles should be at hand at all times, whether it be for emergency mending of tears, or sewing on buttons, or adding trims to special-occasion wear. With a special needle threader, inserting the thread through the eye of the needle is simplicity itself.

SHARPS

A general-purpose hand-sewing needle, with a small, round eye. Available in sizes 1 to 12. For most hand sewing use a size 6 to 9.



CREWEL

Also known as an embroidery needle, a long needle with a long, oval eye that is designed to take multiple strands of embroidery thread.



MILLINERS OR STRAW

A very long, thin needle with a small, round eye. Good for hand sewing and basting as it doesn't damage fabric. A size 8 or 9 is most popular.



QUILTING OR BETWEEN

Similar to a milliner's needle but very short, with a small, round eye. Perfect for fine hand stitches and favored by quilters.



BEADING

Long and extremely fine, to sew beads and sequins to fabric. As it is prone to bending, keep it wrapped in tissue when not in use.



DARNER'S

A long, thick needle that is designed to be used with wool or thick yarns and to sew through multiple layers.



TAPESTRY

A medium-length, thick needle with a blunt end and a long eye. For use with wool yarn in tapestry. Also for darning in serger threads.



CHENILLE

This looks like a tapestry needle but it has a sharp point. Use with thick or wool yarns for darning or heavy embroidery.



BODKIN

A strange-looking needle with a blunt end and a large, fat eye. Use to thread elastic or cord. There are larger eyes for thicker yarns.



SELF-THREADING NEEDLE

A needle that has a double eye. The thread is placed in the upper eye through the gap, then pulled into the eye below for sewing.



WIRE NEEDLE THREADER

A handy gadget, especially useful for needles with small eyes. Also helpful in threading sewing-machine needles.



AUTOMATIC NEEDLE THREADER

This threader is operated with a small lever. The needle, eye down, is inserted and the thread is wrapped around.



Pins

There is a wide variety of pins available, in differing lengths and thicknesses, and ranging from plain household pins to those with colored balls or flower shapes on their ends.



STRAIGHT

General-purpose pins of a medium length and thickness. Can be used for all types of sewing.




QUILTING

A long pin of medium thickness, designed to hold multiple layers of fabric together.




PEARL-HEADED

Longer than household pins, with a colored pearl head. They are easy to pick up and use.



LACE OR BRIDAL

A fine, short pin designed to be used with fine fabrics, such as those for bridal gowns, because the pin will not damage the fabric.



FLOWERHEAD

A long pin of medium thickness with a flat, flower-shaped head. It is designed to be pressed over, as the head lays flat on the fabric.



EXTRA FINE

Extra long and extra fine, this pin is favored by many professional dressmakers, because it is easy to use and doesn't damage finer fabrics.



GLASS-HEADED

Similar to pearl-headed pins but shorter. They have the advantage that they can be pressed over without melting.



DRESSMAKER'S

Similar to a household pin in shape and thickness, but slightly longer. These are the pins for beginners to choose.



SAFETY PINS

Available in a huge variety of sizes and made either of brass or stainless steel. Used for holding two or more layers together.



STAPLE

A strong pin that looks like a very large staple, used for pinning loose covers to furniture. Take care as staple pins are very sharp.



SPIRAL

Shaped like a spiral with a very sharp point at one end to enable it to be twisted in and out easily. Used to secure loose covers to furniture.



PIN CUSHION

To keep pins clean and sharp. Choose a fabric-cover: a foam cushion may blunt pins.

THREADS

There are so many threads available and knowing which ones to choose can be confusing. There are specialist threads designed for special tasks, such as machine embroidery or quilting. Threads also vary in fiber content, from pure cotton to rayon to polyester. Some threads are very fine, while others are thick and coarse. Failure to choose the correct thread can spoil your project and lead to problems with the stitch quality of the sewing machine or serger.

COTTON THREAD

A 100% cotton thread. Smooth and firm, this is designed to be used with cotton fabrics and is much favored by quilters.



BUTTON THREAD

A thicker polyester thread used for decorative top-stitching and buttonholes. Also for hand sewing buttons on thicker fabrics and some soft furnishings.



POLYESTER ALL-PURPOSE THREAD

A cotton-coated polyester thread that has a very slight "give," making it suitable to sew all types of fabrics and garments, as well as soft furnishings. The most popular type of thread.



SILK THREAD

A sewing thread made from 100% silk. Used for machining delicate silk garments. It is also used for basting or temporary stitching in areas that are to be pressed, such as jacket collars, because it can be removed without leaving an imprint.



ELASTIC THREAD

A thin, round elastic thread normally used on the bobbin of the sewing machine for stretch effects such as shirring.



SERGER THREAD



A dull yarn on a larger reel designed to be used on the serger. This type of yarn is normally not strong enough to use on the sewing machine.

**EMBROIDERY THREAD**

Often made from a rayon yarn for shine. This is a finer thread designed for machine embroidery. Available on much larger reels for economy.

**METALLIC THREAD**

A rayon and metal thread for decorative machining and machine embroidery. This thread usually requires a specialist sewing-machine needle.



HABERDASHERY ITEMS

The term haberdashery covers all the bits and pieces that sewers tend to need, for example fasteners such as buttons, snaps, hooks and eyes, and Velcro™. But haberdashery also includes elastics, ribbons, trims of all types, and boning.

Buttons

Buttons can be made from almost anything—shell, bone, coconut, nylon, plastic, brass, silver. They can be any shape, from geometric to abstract to animal shapes. A button may have a shank or have holes on the surface to enable it to be attached to fabric.




Other fasteners

Hooks and eyes (below left), snaps (below center), and Velcro™ (below right) all come in a wide variety of forms, differing in size, shape, and color. Some hooks and eyes are designed to be seen, while snaps and Velcro™ are intended to be hidden fasteners.



Trims, decorations, fringes, and braids

Decorative finishing touches—fringes, strips of sequins, braids, feathers, pearls, bows, flowers, and beads—can dress up a garment, embellish a bag, or personalize soft furnishings. Some are designed to be inserted into seams, while others are surface-mounted.




Ribbons

From the narrowest strips to wide swathes, ribbons are made from a variety of yarns, such as nylon, polyester, and cotton. They can be printed or plain and may feature metallic threads or wired edges.



Elastic

Elastic is available in many forms, from very narrow, round cord to wide strips (below left). It may have buttonhole slots in it (below right) or even have a decorative edge.



Boning

You can buy various types of boning in varying widths. Polyester boning (bottom left), used in boned bodices, can be sewn through, while nylon boning (bottom right), also used on boned bodices, has to be inserted into a casing. Specialist metal boning (below left and right), which may be either straight or spiral, is for corsets and bridal wear.



PRESSING AIDS

Successful sewing relies on successful pressing. Without the correct pressing equipment, sewing can look too “homemade” whereas if correctly pressed, any sewn item will have a neat, professional finish.

MINI IRON ►

Useful to get into small corners and gathers. Use in conjunction with the pressing mat.

IRON ▲

A good-quality steam iron is a wonderful asset. Choose a reasonably heavy iron that has steam and a shot of steam facility.



◄ PRESSING MAT

A heat-resistant mat for pressing small items.



◀ TAILOR'S HAM

A ham-shaped pressing cushion that is used to press darts and the shape into curves of collars and shoulders, and in making tailored garments.



▲ SEAM ROLL

This tubular pressing aid is used to press seams open on fabrics that mark, as the iron only touches the seam on top of the roll. Also used for sleeve and pant seams.



▲ CLAPPER

A wooden aid that pounds creases into a heavy fabric after steaming. The top section is used to help press collar seams and points.



PRESSING CLOTH ▶

Choose a cloth made from silk organza or muslin as you can see through it. The cloth will stop the iron from marking fabric and prevent burning delicate fabrics.



▲ IRONING BOARD

Essential to iron on. Make sure the board is height-adjustable.

PRESSING MITTEN ▶

Slips on to your hand to enable more control over where you are pressing.



▼ VELVET MAT

A pressing mat with a tufted side to aid the pressing of pile fabrics, such as velvet.



SEWING MACHINE

A sewing machine will quickly speed up any job, whether it be a quick repair or a huge home-sewing project. Most sewing machines today are aided by computer technology, which enhances stitch quality and ease of use. Always spend time trying out a sewing machine before you buy, to really get a feel for it.

THREADING GUIDES

Markings to help guide you in threading the machine.

TENSION DIAL

To control the stitch tension on the upper thread, i.e. how fast the thread feeds through the sewing machine.

AUTOMATIC NEEDLE THREADER

A pull-down gadget to aid threading the machine needle.

BUTTONHOLE SENSOR

A pull-down sensor that automatically judges the size of the buttonhole required to fit the button chosen.

PRESSER FOOT

To hold the fabric in place while stitching. Various feet can be used here to aid different sewing processes. See pages 32–33.

DOG FEEDS

These metal teeth grip the fabric and feed it through the machine.

REMOVABLE FREE ARM

This section of the machine will pull away to give a narrow work bed that can be used when inserting sleeves. It also contains a useful storage section.

NEEDLE


The machine needle. Replace regularly to ensure good stitch quality. See page 32.


SHANK

To hold the various feet in place.

NEEDLE PLATE

A transparent removable cover reveals the bobbin. This plate is gridded to help stitch seams of various widths.





Sewing-machine accessories

Many accessories can be purchased for your sewing machine to make certain sewing processes so much easier. There are different machine needles not only for different fabrics, but also for different types of threads. There is also a huge number of sewing-machine feet, and new feet are constantly coming on to the market. Those shown here are some of the most popular.



PLASTIC BOBBIN

The bobbin is for the lower thread. Some machines take plastic bobbins, others metal. Always check which kind of bobbin your machine uses as the incorrect choice can cause stitch problems.



METAL BOBBIN

Also known as a universal bobbin, this is used on many types of sewing machines. Be sure to check that your machine needs a metal bobbin before you buy.



MACHINE NEEDLES

There are different types of sewing machine needles to cope with different fabrics. Machine needles are sized from 60 to 100, a 60 being a very fine needle. There are special needles for machine embroidery and also for metallic threads.



OVEREDGE FOOT

A foot that runs along the raw edge of the fabric and holds it stable while an overedge stitch is worked.



EMBROIDERY FOOT

A clear plastic foot with a groove underneath that allows linear machine embroidery stitches to pass under.



FREE EMBROIDERY OR DARNING FOOT

A foot designed to be used when the dog feeds on the machine are lowered. This enables a free motion stitch to be worked.



BUTTONHOLE FOOT

This extends and the button is placed in the back of the foot. The machine will stitch a buttonhole to fit due to the buttonhole sensor.




BLIND HEM FOOT

Use this foot in conjunction with the blind hem stitch to create a neat hemming stitch.



ROLLED HEM FOOT

This foot rolls the fabric while stitching with a straight stitch or a zigzag stitch.

**WALKING FOOT**

This odd-looking foot “walks” across the fabric, so that the upper layer of fabric does not push forward. Great for matching checkers and stripes and also for difficult fabrics, like quilts.

**ZIPPER FOOT**

This foot fits to either the right or left-hand side of the needle to enable you to stitch close to a zipper.

**INVISIBLE ZIPPER FOOT**

A foot that is used to insert a concealed zipper—the foot holds open the coils of the zipper, enabling you to stitch behind them.

**PIN TUCK FOOT**

A foot with grooves underneath to allow multiple pin tucks to be sewn.

**PIPING FOOT**

A deep groove in this foot allows a piping cord to fit underneath, enabling close stitching to the cord.

**RIBBON FOOT**

A foot that will feed either one or two ribbons evenly under the machine needle to ensure accurate stitching.

**BEADING FOOT, NARROW**

This foot has a narrow groove and is used to attach small beads or decorative cords.

**BEADING FOOT, WIDE**

Beads on a string will fit under the foot, which has a wide groove, and they can then be zigzag stitched over.

**ULTRA-GLIDE FOOT**

A foot made from Teflon™ that glides over the fabric. Useful for synthetic leathers.

SERGER

SERGER STITCHES

As the serger works, the threads wrap around the edge to give a professional finish. The 3-thread stitch is used primarily for neatening. A 4-thread stitch can also be used for neatening, as well as for construction due to its having the extra thread.

3-THREAD SERGER STITCH



4-THREAD SERGER STITCH



This machine is often used in conjunction with the sewing machine as it gives a very professional finish to your work. The serger has two upper threads and two lower threads (the loopers), with a knife that removes the edge of the fabric. Used extensively for neatening the edges of fabric, it can also be used for construction of stretch knits.

Serger accessories

You can purchase additional feet for the serger. Some will speed up your sewing by performing tasks such as gathering.



SERGER NEEDLES

The serger uses a ballpoint needle, which creates a large loop in the thread for the loopers to catch and produce a stitch. If a normal sewing machine needle is used, it could damage the serger.



SERGER FOOT

The standard foot used for most processes.



GATHERING FOOT

This gadget enables one layer of fabric to be gathered and stitched to a non-gathered layer, all in one application. Especially suitable for net and fine fabrics.



CORDING FOOT

A foot with a coil on the one side through which a thin cord or fishing line is fed. Use in conjunction with a rolled hem setting for decorative effects.



EMBROIDERY MACHINE

A machine that does not sew but embroiders, this enables you to produce embellished clothing or home wares. Computer-controlled, the machine has plenty of built-in embroidery designs and there are many more designs that can be purchased to use with it. The machine works best with special embroidery threads and bobbin threads.

EMBROIDERY DESIGNS

Here are some examples of the many types of design that can be stitched out, to personalize and embellish clothing and accessories as well as place mats, tablecloths, serviettes, pillows, baby blankets, and many other items.



Embroidery machine accessories

Hoops of varying shapes and sizes fit on to the machine carriage to enable the embroidery to be stitched.

A gridded template on the bottom of the embroidery hoop aids placement of the design.



Once the fabric is stretched in the hoop, the ring is pressed down and secured. The fabric must be held taut.



TENSION DIAL

To control the tension in the upper thread.

SPOOL HOLDER

To hold the machine embroidery thread.

SCISSOR CUTTER

This button cuts the embroidery threads when you need to change colors or have completed your design.

BOBBIN WINDER

To wind the bobbins. An embroidery machine requires bobbin thread, which is a slightly finer thread.

LCD SCREEN

A touch screen from which you choose your design and program the machine. The screen allows you to build up your own design by combining different components.

START/STOP BUTTON

This machine has no foot control as it will sew on its own! Use this button to start and stop it.

AUTOMATIC NEEDLE THREADER


To aid threading the machine needle.


NEEDLE AND FOOT

The machine needle and embroidery foot.

HOOP

The embroidery hoop in position.







FABRICS

Fabric is made from fibers. Each fiber is like a small hair. A great number are twisted together to make a yarn, which can then be woven or knitted into fabric. Whether making clothes, soft furnishings, or crafts, it's important to choose the right fabric for your project. When buying, look at the fabric carefully in the store. Feel it, and crease it in your hand. Then ask yourself if it will be suitable. You also need to consider the width of the fabric, the cost, and the care—some have to be dry-cleaned.

Wool fabrics

A natural fiber, wool comes primarily from sheep—Australian merino sheep's wool is considered to be the best. However, we also get wool fibers from goats (mohair and cashmere), rabbits (angora), camels (camel hair), and llamas (alpaca). A wool fiber is either short and fluffy, when it is known as a woollen yarn, or it is long, strong, and smooth, when it is called worsted. The term virgin (or new) wool denotes wool fibers that are being used for the first time. Wool may be reprocessed or reused and is then often mixed with other fibers.

PROPERTIES OF WOOL

- comfortable to wear in all climates as it is available in many weights and weaves
- warm in the winter and cool in the summer, because it will breathe with your body
- absorbs moisture better than other natural fibers—will absorb up to 30 percent of its weight before it feels wet
- flame-resistant
- relatively crease-resistant
- ideal to tailor as it can be easily shaped with steam
- often blended with other fibers to reduce the cost of fabric
- felts if exposed to excessive heat, moisture, and pressure
- will be bleached by sunlight with prolonged exposure
- can be damaged by moths

CASHMERE

Wool from the Kashmir goat, and the most luxurious of all the wools. A soft yet hard-wearing fabric available in different weights.

Cutting out: as cashmere often has a slight pile, use a nap layout

Seams: plain, neatened with serger stitch or pinking shears (a zigzag stitch would curl the edge of the seam)

Thread: a silk thread is ideal, or a polyester all-purpose thread

Needle: machine size 12/14, depending on the thickness of the fabric; sharps for hand sewing

Pressing: steam iron on a steam setting, with a pressing cloth and seam roll

Use for: jackets, coats, men's wear; knitted cashmere yarn for sweaters, cardigans, underwear



CHALLIS

A fine wool fabric, made from a worsted yarn that has an uneven surface texture. Challis is often printed as well as plain.

Cutting out: a nap layout is not required unless the fabric is printed

Seams: plain, neatened with serger or zigzag stitch; a run and fell seam can also be used

Thread: polyester all-purpose thread

Needle: machine size 11/12; sharps for hand sewing

Pressing: steam iron on a steam setting, with a pressing cloth; fabric will stretch while warm so handle with care

Use for: dresses, jackets, garments with pleating or draping detail



CREPE

A soft fabric made from a twisted yarn, which is what produces the uneven surface. It is important to preshrink this fabric prior to use by giving it a good steaming, because it will have stretched on the bolt and it is prone to shrinkage.

Cutting out: use a regular layout


Seams: plain, neatened with serger (a zigzag stitch may curl the edge of the seam)

Thread: polyester all-purpose thread

Needle: machine size 12; sharps or milliner's for hand sewing

Pressing: steam iron on a wool setting; a pressing cloth is not always required

Use for: all types of clothing



FLANNEL

A wool with a lightly brushed surface, featuring either a plain or twill weave. Used in the past for underwear.

Cutting out: use a nap layout

Seams: plain, neatened with serger or zigzag stitch or Hong Kong finish

Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a wool setting with a pressing cloth; use a seam roll as the fabric is prone to marking

Use for: coats, jackets, skirts, men's wear

**GABARDINE**

A hard-wearing suiting fabric with a distinctive weave. Gabardine often has a sheen and is prone to shine. It can be difficult to handle as it is springy and frays badly.

Cutting out: a nap layout is advisable as the fabric has a sheen

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread or 100% cotton thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a wool setting; use just the toe of the iron and a silk organza pressing cloth as the fabric will mark and may shine

Use for: men's wear, jackets, pants

**MOHAIR**

From the wool of the Angora goat. A long, straight, and very strong fiber that produces a hairy cloth.

Cutting out: use a nap layout, with the fibers brushing down the pattern pieces in the same direction, from neck to hem

Seams: plain, neatened with serger or pinking shears

Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a wool setting; "stroke" the iron over the wool, moving in the direction of the nap

Use for: jackets, coats, men's wear, soft furnishings; knitted mohair yarns for sweaters

**TARTAN**

An authentic tartan belongs to a Scottish clan, and each has its own unique design that can only be used by that clan. The fabric is made using a twill weave from worsted yarns.

Cutting out: check the design for even/uneven check as it may need a nap layout or even a single layer layout

Seams: plain, matching the pattern and neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a wool setting; may require a pressing cloth, so test first

Use for: traditionally kilts, but these days also skirts, pants, jackets, soft furnishings



TWEED, MODERN

A mix of chunky and nobbly wool yarns. Modern tweed is often found in contemporary color palettes as well as plain, and with interesting fibers in the weft such as metallics and paper. It is much favored by fashion designers.

Cutting out: use a nap layout


Seams: plain, neatened with serger or zigzag stitch; the fabric is prone to fraying

Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a wool setting; a pressing cloth may not be required

Use for: jackets, coats; also skirts, dresses, soft furnishings

**TWEED, TRADITIONAL**

A rough fabric with a distinctive warp and weft, usually in different colors, and often forming a small check pattern. Traditional tweed is associated with the English countryside.

Cutting out: a nap layout is not required unless the fabric features a check

Seams: plain, neatened with serger or zigzag stitch; can also be neatened with pinking shears

Thread: polyester all-purpose thread or 100% cotton thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a steam setting; a pressing cloth may not be required

Use for: jackets, coats, skirts, men's wear, soft furnishings

**VENETIAN**

A wool with a satin weave, making a luxurious, expensive fabric.

Cutting out: use a nap layout

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread or 100% cotton thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a steam setting with a silk organza cloth to avoid shine; use a seam roll under the seams to prevent them from showing through

Use for: jackets, coats, men's wear

**WOOL WORSTED**

A light and strong cloth, made from good-quality thin, firm filament fibers. Always steam prior to cutting out as the fabric may shrink slightly after having been stretched around a bolt.

Cutting out: use a nap layout


Seams: plain, neatened with serger or zigzag stitch or Hong Kong finish

Thread: polyester all-purpose thread

Needle: machine size 12/14, depending on fabric; milliner's or sharps for hand sewing

Pressing: steam iron on a wool setting, with a pressing cloth; use a seam roll to prevent the seam from showing through

Use for: skirts, jackets, coats, pants



Cotton fabrics

One of the most versatile and popular of all fabrics, cotton is a natural fiber that comes from the seed pods, or bolls, of the cotton plant. It is thought that cotton fibers have been in use since ancient times. Today, the world's biggest producers of cotton include the United States, India, and countries in the Middle East. Cotton fibers can be filament or staple, with the longest and finest used for top-quality bed linen. Cotton clothing is widely worn in warmer climates as the fabric will keep you cool.

PROPERTIES OF COTTON

- absorbs moisture well and carries heat away from the body
- stronger wet than dry
- does not build up static electricity
- dyes well
- prone to shrinkage unless it has been treated
- will deteriorate from mildew and prolonged exposure to sunlight
- creases easily
- soils easily, but launders well

BRODERIE ANGLAISE

A fine, plain-weave cotton that has been embroidered in such a way as to make small holes. Usually white or a pastel color.

Cutting out: may need layout to place embroidery at hem edge

Seams: plain, neatened with serger or zigzag stitch; a French seam can also be used

Thread: polyester all-purpose thread

Needle: machine size 12/14; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth is not required

Use for: baby clothes, summer skirts, blouses



CALICO

A plain weave fabric that is usually unbleached and quite stiff. Available in many different weights, from very fine to extremely heavy.

Cutting out: use a regular layout

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 11/14, depending on thickness of thread; sharps for hand sewing

Pressing: steam iron on a steam setting; a pressing cloth is not required

Use for: toiles (test garments), soft furnishings



CHAMBRAY

A light cotton that has a colored warp thread and white weft thread. Chambray can also be found as a check or a striped fabric.

Cutting out: use a regular layout

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 11; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth is not required

Use for: blouses, men's shirts, children's wear



CHINTZ

A floral print or plain cotton fabric with a glazed finish that gives it a sheen. It has a close weave and is often treated to resist dirt.

Cutting out: use a nap layout

Seams: plain, neatened with serger or zigzag stitch; a run and fell seam can also be used

Thread: polyester all-purpose thread or 100% cotton thread

Needle: machine size 14; milliner's for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth may be required due to sheen on fabric

Use for: soft furnishings



CORDUROY

A soft pile fabric with distinctive stripes (known as wales or ribs) woven into it. The name depends on the size of the ribs: baby or pin cord has extremely fine ribs; needle cord has slightly thicker ribs; corduroy has 10–12 ribs per 1 in (2.5 cm); and elephant or jumbo cord has thick, heavy ribs.

Cutting out: use a nap layout with the pile on the corduroy, brushing the pattern pieces from neck to hem, to give depth

Seams: plain, stitched using a walking foot and neaten with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 12/16; sharps or milliner's for hand sewing

Pressing: steam iron on a cotton setting; use a seam roll under the seams with a pressing cloth

Use for: pants, skirts, men's wear

**CRINKLE COTTON**

Looks like an exaggerated version of seersucker (see p46), with creases added by a heat process. Crinkle cotton may require careful laundering as it often has to be twisted into shape when wet to put the creases back in.

Cutting out: a nap layout is not required unless the fabric is printed

Seams: plain, neaten with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 12; milliner's for hand sewing

Pressing: steam iron on a cotton setting; take care not to press out the crinkles

Use for: blouses, dresses, children's wear

**DAMASK**

A cotton that has been woven on a jacquard loom to produce a fabric usually with a floral pattern in a self color. May have a sheen to the surface.

Cutting out: use a nap layout

Seams: plain, neaten with serger or zigzag stitch

Thread: polyester all-purpose thread or 100% cotton thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth may be required if the fabric has a sheen

Use for: home furnishings; colored jacquards for jackets, skirts

**DENIM**

Named after Nîmes in France. A hard-wearing twill-weave fabric (see p53) with a colored warp and white weft, usually made into jeans. Available in various weights and often mixed with an elastic thread for stretch. Denim is usually blue, but is also available in a variety of other colors.

Cutting out: use a regular layout

Seams: run and fell or top-stitched plain

Thread: polyester all-purpose thread with top-stitching thread for detail top-stitching

Needle: machine size 14/16; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth should not be required

Use for: jeans, jackets, children's wear



DRILL

A hard-wearing twill or plain-weave fabric with the same color warp and weft. Drill frays badly on the cut edges.

Cutting out: use a regular layout

Seams: run and fell; or plain, neaten with serger or zigzag stitch

Thread: polyester all-purpose thread with top-stitching thread for detail top-stitching

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth is not required

Use for: men's wear, casual jackets, pants

**GINGHAM**

A fresh, two-color cotton fabric that features checkers of various sizes. A plain weave made by having groups of white and colored warp and weft threads.

Cutting out: usually an even check, so nap layout is not required but recommended; pattern will need matching


Seams: plain, neaten with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 11/12; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth should not be required

Use for: children's wear, dresses, shirts, home furnishings

**JERSEY**

A fine cotton yarn that has been knitted to give stretch, making the fabric very comfortable to wear. Jersey will also drape well.

Cutting out: a nap layout is recommended

Seams: 4-thread serger stitch; or plain seam stitched with a small zigzag stitch and then seam allowances stitched together with a zigzag

Thread: polyester all-purpose thread

Needle: machine size 12/14; a ballpoint needle may be required for serger and for hand sewing

Pressing: steam iron on a wool setting as jersey may shrink on a cotton setting

Use for: underwear, drapery dresses, leisurewear, bedding

**MADRAS**

A plaid fabric made from a fine cotton yarn, usually from India. Often found in bright colors. An inexpensive cotton fabric.

Cutting out: use a nap layout and match the pattern

Seams: plain, neaten with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 12/14; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth is not required

Use for: shirts, skirts, home furnishings



MUSLIN

A fine, plain, open-weave cotton. Can be found in colors but usually sold a natural/unbleached or white. Makes great pressing cloths and interlinings. It is a good idea to wash prior to use.

Cutting out: use a regular layout

Seams: 4-thread serger stitch; or plain seam, neatened with serger or zigzag stitch; a French seam could also be used

Thread: polyester all-purpose thread

Needle: machine size 11; milliner's for hand sewing

Pressing: steam iron on a cotton setting; a cloth is not required

Use for: curtaining and other household uses, as well as test patterns or toiles

**SEERSUCKER**

A woven cotton that has a bubbly appearance woven into it, due to stripes of puckers. Do not over-press, or the surface effect will be damaged.

Cutting out: use a nap layout, due to puckered surface effect

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 11/12; milliner's for hand sewing

Pressing: steam iron on a cotton setting (be careful not to press out the wrinkles)

Use for: summer clothing, skirts, shirts, children's wear

**SHIRTING**

A closely woven, fine cotton, with colored warp and weft yarns making stripes or checks.

Cutting out: use a nap layout if fabric has uneven stripes

Seams: plain, neatened with serger or zigzag stitch; a run and fell seam can also be used

Thread: polyester all-purpose thread

Needle: machine size 12; milliner's for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth is not required

Use for: ladies' and men's shirts

**TERRY CLOTH**

A cotton fabric with loops on the surface; top-quality terry cloth has loops on both sides. It is highly absorbent. Wash before use to preshrink and make it fluffy.

Cutting out: use a nap layout


Seams: 4-thread serger stitch; or plain seam, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth is not required

Use for: bathrobes, beachwear

**VELVET**

A pile-weave fabric, made by using an additional yarn that is then cut to produce the pile. Difficult to handle and can be easily damaged if seams have to be unpicked.

Cutting out: use a nap layout with the pile brushing up from hem to neck, to give depth of color

Seams: plain, stitched using a walking foot (stitch all seams from

hem to neck) and neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 14; milliner's for hand sewing

Pressing: only if you have to; use a velvet board, a bit of steam, toe of iron, and silk organza cloth

Use for: jackets, coats



Silk fabrics

Often referred to as the queen of all fabrics, silk is made from the fibers of the silkworm's cocoon. This strong and luxurious fabric dates back thousands of years to its first development in China, and the secret of silk production was well protected by the Chinese until 300AD. Silk fabrics can be very fine or thick and chunky. They need careful handling as some silk fabrics can be easily damaged.

PROPERTIES OF SILK

- keeps you warm in winter and cool in summer
- absorbs moisture and dries quickly
- dyes well, producing deep, rich colors
- static electricity can build up and fabric may cling
- will fade in prolonged strong sunlight
- prone to shrinkage
- best dry-cleaned
- weaker when wet than dry
- may water-mark

CHIFFON

A very strong and very fine, transparent silk with a plain weave. Will gather and ruffle well. Difficult to handle.

Cutting out: place tissue paper under the fabric and pin the fabric to the tissue, cutting through all layers if necessary; use extra-fine pins

Seams: French

Thread: polyester all-purpose thread

Needle: machine size 9/11; fine milliner's for hand sewing

Pressing: dry iron on a wool setting

Use for: special-occasion wear, over-blouses



CREPE DE CHINE

Medium weight, with an uneven surface due to the twisted silk yarn used. Drapes well and often used on bias-cut garments.

Cutting out: if to be bias-cut, use a single layer layout; otherwise use a nap layout

Seams: a seam for a difficult fabric or French

Thread: polyester all-purpose thread

Needle: machine size 11; milliner's or between for hand sewing

Pressing: dry iron on a wool setting

Use for: blouses, dresses, special-occasion wear



DUCHESS SATIN

A heavy, expensive satin fabric used almost exclusively for special-occasion wear.

Cutting out: use a nap layout

Seams: plain, with pinked edges

Thread: polyester all-purpose thread

Needle: machine size 12/14; milliner's for hand sewing

Pressing: steam iron on a wool setting with a pressing cloth; use a seam roll under the seams to prevent shadowing

Use for: special-occasion wear



DUPION

Similar to hand-woven dupion (see page 48) but woven using a much smoother yarn to reduce the amount of nubby bits in the weft.

Cutting out: use a nap layout to prevent shadowing

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 12; milliner's for hand sewing

Pressing: steam iron on a wool setting, with a pressing cloth as fabric may water-mark

Use for: dresses, skirts, jackets, special-occasion wear, soft furnishings



DUPION, HAND-WOVEN

The most popular of all the silks. A distinctive weft yarn with many nubby bits. Available in hundreds of colors. Easy to handle, but it does fray badly.

Cutting out: use a nap layout as the fabric shadows

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 12; milliner's for hand sewing

Pressing: steam iron on a wool setting, with a pressing cloth to avoid water-marking

Use for: dresses, special-occasion wear, jackets, soft furnishings

**GEORGETTE**

A soft, filmy silk fabric that has a slight transparency. Does not crease easily.

Cutting out: place tissue paper under the fabric and pin fabric to tissue, cutting through all layers if necessary; use extra-fine pins

Seams: French

Thread: polyester all-purpose thread

Needle: machine size 11; milliner's for hand sewing

Pressing: dry iron on a wool setting to avoid damage by steam

Use for: special-occasion wear, loose-fitting overshirts

**HABUTAI**

Originally from Japan, a smooth, fine silk that can have a plain or a twill weave. Fabric is often used for silk painting.

Cutting out: use a regular layout


Seams: French

Thread: polyester all-purpose thread

Needle: machine size 9/11; very fine milliner's or between's for hand sewing

Pressing: steam iron on a wool setting

Use for: lining, shirts, blouses

**MATKA**

A silk suiting fabric with an uneven-looking yarn. Matka can be mistaken for linen.

Cutting out: use a nap layout as silk may shadow

Seams: plain, neatened with serger or zigzag stitch or Hong Kong finish

Thread: polyester all-purpose thread

Needle: machine size 12/14; milliner's for hand sewing

Pressing: steam iron on a wool setting with a pressing cloth; a seam roll is recommended to prevent the seams from showing through

Use for: dresses, jackets, pants



ORGANZA

A sheer fabric with a crisp appearance that will crease easily.

Cutting out: use a regular layout

Seams: French or a seam for a difficult fabric

Thread: polyester all-purpose thread

Needle: machine size 11; milliner's or between for hand sewing

Pressing: steam iron on a wool setting; a pressing cloth should not be required

Use for: sheer blouses, shrugs, interlining, interfacing

**SATIN**

A silk with a satin weave that can be very light to quite heavy in weight.

Cutting out: use a nap layout in a single layer as fabric is slippery

Seams: French; on thicker satins, a seam for a difficult fabric

Thread: polyester all-purpose thread (not silk thread as it becomes weak with wear)

Needle: machine size 11/12; milliner's or between for hand sewing

Pressing: steam iron on a wool setting, with a pressing cloth as fabric may water-mark

Use for: blouses, dresses, special-occasion wear

**SILK AND WOOL MIX**

A fabric made by mixing wool and silk fibers or wool and silk yarns. The fabric made may be fine in quality or thick, like a coating.

Cutting out: use a nap layout

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 11/14, depending on fabric; sharps for hand sewing

Pressing: steam iron on a wool setting; seams will require some steam to make them lie flat

Use for: suits, skirts, pants, coats

**TAFFETA**

A smooth, plain-weave fabric with a crisp appearance. It makes a rustling sound when worn. Can require special handling and does not wear well.

Cutting out: use a nap layout, with extra-fine pins in seams as they will mark the fabric

Seams: plain; fabric may pucker, so sew from the hem upward, keeping the fabric taut under the machine; neaten with serger or pinking shears

Thread: polyester all-purpose thread

Needle: machine size 11; milliner's or between for hand sewing

Pressing: cool iron, with a seam roll under the seams

Use for: special-occasion wear



Linen fabrics

Linen is a natural fiber that is derived from the stem of the flax plant. It is available in a variety of qualities and weights, from very fine linen to heavy suiting weights. Coarser than cotton, it is sometimes woven with cotton as well as being mixed with silk.

PROPERTIES OF LINEN

- cool and comfortable to wear
- absorbs moisture well
- shrinks when washed
- does not ease well
- has a tendency to wrinkle
- prone to fraying
- resists moths but is damaged by mildew

COTTON AND LINEN MIX

Two fibers may have been mixed together in the yarn or may have mixed warp and weft yarns. It has lots of texture in the weave. Silk and linen mix is treated in the same way.

Cutting out: use a regular layout

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing

Pressing: a steam iron on a steam setting, with a silk organza pressing cloth

Use for: summer-weight jackets, tailored dresses



DRESS-WEIGHT LINEN

A medium-weight linen with a plain weave. The yarn is often uneven, which causes slubs in the weave.

Cutting out: use a regular layout

Seams: plain, neatened with serger or zigzag stitch or a Hong Kong finish

Thread: polyester all-purpose thread with a top-stitching thread for top-stitching

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a cotton setting

Use for: dresses, pants, skirts



PRINTED LINENS

Many linens today feature prints or even embroidery. The fabric may be light to medium weight, with a smooth yarn that has few slubs.

Cutting out: use a nap layout

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a cotton setting (steam is required to remove creases)

Use for: dresses, skirts



SUITING LINEN

A heavier yarn is used to produce a linen suitable for suits for men and women. Can be a firm, tight weave or a looser weave.

Cutting out: use a regular layout


Seams: plain, neatened with serger or a zigzag stitch and sharps hand-sewing needle

Thread: polyester all-purpose thread with a top-stitch thread for top-stitching

Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a cotton setting (steam is required to remove creases)

Use for: men's and women's suits, pants, coats



Leather and suede

Leather and suede are natural fabrics derived from either pigskin or cowhide. Depending on the curing process that has been used, the skin will be either a suede or a leather. The fabrics require special handling.

LEATHER AND SUEDE

The pattern pieces cannot be pinned on to leather and suede—you must draw around them using tailor's chalk. After cutting out, the chalk will rub off and not damage the skin.

Cutting out: a complete pattern is required, left and right-hand halves; use

a nap layout for suede, as it will brush one way

Seams: lapped or plain, using a walking foot or an ultra glide foot; neatening is not required


Thread: polyester all-purpose thread

Needle: machine size 14 (a special leather needle

may actually damage the skin); hand sewing is not recommended

Pressing: Avoid steam when ironing; set the iron on the rayon setting and use a 100% cotton cloth between the iron and leather

Use for: skirts, pants, jackets, soft furnishings



Manmade fabrics

The term "manmade" applies to any fabric that is not 100 percent natural. Many of these fabrics have been developed over the last hundred years, which means they are new compared to natural fibers. Some manmade fabrics are made from natural elements mixed with chemicals while others are made entirely from non-natural substances. The properties of manmade fabrics vary from fabric to fabric.

ACETATE

Introduced in 1924, acetate is made from cellulose and chemicals. The fabric has a slight shine and is widely used for linings. Acetate can also be woven into fabrics such as acetate taffeta, acetate satin, and acetate jersey.

Properties of acetate:

- dyes well
- can be heat-set into pleats
- washes well

Cutting out: use a nap layout due to sheen on fabric

Seams: plain, neatened with serger or zigzag stitch, or 4-thread serger stitch

Thread: polyester all-purpose thread

Needle: machine size 11; sharps for hand sewing

Pressing: steam iron on a cool setting (fabric can melt)

Use for: special-occasion wear, linings



ACRYLIC

Introduced in 1950, acrylic fibers are made from ethylene and acrylonitrile. The fabric resembles wool and makes a good substitute for machine-washable wool. Often seen as a knitted fabric, the fibers can be mixed with wool.

Properties of acrylic:

- little absorbency
- tends to retain odors
- not very strong

Cutting out: use a regular layout

Seams: 4-thread serger stitch on knitted fabrics; plain seam on woven fabrics

Thread: polyester all-purpose thread

Needle: machine size 12/14, but a ballpoint needle may be required on knitted fabrics; sharps for hand sewing

Pressing: steam iron on a wool setting (fabric can be damaged by heat)

Use for: knitted yarns for sweaters; wovens for skirts, blouses



NYLON

Developed by DuPont in 1938, the fabric takes its name from a collaboration between New York (NY) and London (LON). Nylon is made from polymer chips that are melted and extruded into fibers. The fabric can be knitted or woven.

Properties of nylon:

- very hard-wearing

- does not absorb moisture
- washes easily, although white nylon can discolor easily
- very strong

Cutting out: a nap layout is not required unless the fabric is printed

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 14, but a ballpoint needle may be required for knitted nylons; sharps for hand sewing

Pressing: steam iron on a silk setting (fabric can melt)

Use for: sportswear, underwear



POLYESTER

One of the most popular of the manmade fibers, polyester was introduced in 1951 as a washable man's suit. Polyester fibers are made from petroleum by-products and can take on any form, from a very fine sheer fabric to a thick, heavy suiting.

Properties of polyester:

- non-absorbent
- does not crease
- can build up static
- may "pill"

Cutting out: a nap layout is only required if the fabric is printed

Seams: French, plain, or 4-thread serger, depending on the weight of the fabric

Thread: polyester all-purpose thread

Needle: machine size 11/14; sharps for hand sewing

Pressing: steam iron on a polyester setting

Use for: workwear, school uniforms

**RAYON**

Also known as viscose and often referred to as artificial silk, this fiber was developed in 1889. It is made from wood pulp or cotton linters mixed with chemicals. Rayon can be knitted or woven and made into a wide range of fabrics. It is often blended with other fibers.

Properties of rayon:

- is absorbent
- is not static
- dyes well
- frays badly

Cutting out: a nap layout is only required if the fabric is printed

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 12/14; sharps for hand sewing

Pressing: steam iron on a silk setting

Use for: dresses, blouses, jackets

**SPANDEX**

Introduced in 1958, this is a lightweight, soft fiber that can be stretched 500% without breaking. A small amount of spandex is often mixed with other fibers to produce wovens with a slight stretch.

Properties of spandex:

- resistant to body oils, detergents, sun, sea, and sand

- can be difficult to sew
- can be damaged by heat
- not suitable for hand sewing

Cutting out: use a nap layout

Seams: 4-thread serger stitch or a seam stitched with a small zigzag

Thread: polyester all-purpose thread

Needle: machine ballpoint size 14 or a machine stretch needle

Pressing: steam iron on a wool setting (spandex can be damaged by a hot iron)

Use for: swimwear, foundation wear, sportswear

**SYNTHETIC FURS**

Created using a looped yarn that is then cut on a knitted or a woven base, synthetic fur can be made from nylon or acrylic fibers. The furs vary tremendously in quality and some are very difficult to tell from the real thing.

Properties of synthetic furs:

- easy to sew
- require careful sewing

- can be heat-damaged by pressing
- not as warm as real fur

Cutting out: use a nap layout, with the fur pile brushed from the neck to the hem; cut just the backing carefully and not through the fur pile

Seams: plain, with a longer stitch and a walking foot; no neatening is required

Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing

Pressing: if required, use a cool iron (synthetic fur can melt under a hot iron)

Use for: outerwear

**SYNTHETIC LEATHER AND SUEDE**

Made from polymers, these are non-woven fabrics. Some synthetic leathers and suedes can closely resemble the real thing.

Properties of synthetic leather and suede:

- do not fray
- do not ease well

- can be difficult to sew by hand, so this is not recommended

Cutting out: use a nap layout

Seams: plain, stitched using a walking foot and neatened with pinking shears; can also use top-stitched seams and lapped seams

Thread: polyester all-purpose thread

Needle: machine size 11/14

Pressing: steam iron on a wool setting, with a pressing cloth

Use for: jackets, skirts, pants, soft furnishings




Fabric construction

Most fabric is made by either knitting or weaving. A knitted fabric is constructed by interlocking looped yarns. For a woven fabric, horizontal and vertical yarns go under and over each other. The warp yarn, which is the strongest, runs vertically and the weft crosses it at right angles. There are also non-woven fabrics created by a felting process where tiny fibers are mixed and squeezed together, then rolled out.



PLAIN WEAVE

As the name suggests, this is the simplest of all the weaves. The weft yarn passes under one warp yarn, then over another one.





SATIN WEAVE

This has a long strand known as a float on the warp yarn. The weft goes under four warp yarns, then over one. This weave gives a sheen on the fabric.




HERRINGBONE WEAVE

The distinctive herringbone zigzag weave is made by the weft yarn going under and over warp yarns in a staggered pattern.




TWILL WEAVE

The diagonal twill weave is made by the weft yarn going under two warp yarns, then over another two, with the pattern moved one yarn across each time.




WARP KNIT

This is made on a knitting machine, where one yarn is set to each needle (latch). The knit is formed in a vertical and diagonal direction.



WEFT KNIT

Made in the same way as knitting by hand on needles, this uses one yarn that runs horizontally.



Interfacings

An interfacing is a piece of fabric that is attached to the main fabric to give it support or structure. An interfacing fabric may be woven, knitted, or non-woven. It may also be fusible or non-fusible. A fusible interfacing (also called iron-on) can be bonded to the fabric by applying heat, whereas a non-fusible interfacing needs to be sewn to the fabric with a basting stitch. Always cut interfacings on the same grain as the fabric, regardless of its construction.

FUSIBLE INTERFACINGS

Be sure to buy fusibles designed for the home sewer, because the adhesive on the back of fusible interfacings for commercial use

cannot be released with a normal steam iron. Do all pattern marking after the interfacing has been applied to the fabric.

WOVEN

A woven fusible is always a good choice for a woven fabric as the two weaves will work together. Always cut on the same grain as the fabric. This type of interfacing is suitable for crafts and for more structured garments.



LIGHTWEIGHT WOVEN

A very light, woven fusible that is almost sheer, this can be difficult to cut out as it tends to stick to the scissors. It is suitable for all light to medium-weight fabrics.




KNITTED

A knitted fusible is ideally suited to a knit fabric as the two will be able to stretch together. Some knitted fusibles only stretch one way, while others will stretch in all directions. A knitted fusible is also a good choice on fabrics that have a percentage of stretch.



NON-WOVEN

Non-woven fusibles are available in a wide variety of weights—choose one that feels lighter than your fabric. You can always add a second layer if one interfacing proves to be too light. This interfacing is suitable for supporting collars and cuffs, and facings on garments.



HOW TO APPLY A FUSIBLE INTERFACING



- 1 Place fabric on pressing surface, wrong side up, making sure it is straight and not wrinkled.
- 2 Place the chosen interfacing sticky side down on the fabric (the sticky side feels gritty).
- 3 Cover with a dry pressing cloth and spray the cloth with a fine mist of water.
- 4 Place a steam iron, on a steam setting, on top of the pressing cloth.

- 5 Leave the iron in place for at least 10 seconds before moving it to the next area of fabric.

- 6 Check to see if the interfacing is fused to the fabric by rolling the fabric—if the interfacing is still loose in places, repeat the pressing process.

- 7 When the fabric has cooled down, the fusing process will be complete. Then pin the pattern back on to the fabric and transfer the pattern markings as required.

NON-FUSIBLE INTERFACINGS

These sew-in interfacings require basting to the wrong side of facings or the main garment fabric around the seam allowances. They are

useful for sheer or fine fabrics where the adhesive from a fusible interfacing might show through.

ALPACA

A tailoring's canvas made from wool and alpaca, this interfacing is excellent to use in difficult fabrics such as velvet, because the alpaca can be steamed into shape.



COLLAR CANVAS

A firm, white cotton canvas, this will stiffen shirt collars and also boned bodices. It is available as firm and soft collar canvas although there is little difference between the two. Collar canvas is also useful in crafts, such as handbags.



MUSLIN

A cotton muslin interfacing is a good choice on summer dresses as well as for special-occasion wear. Muslin can also be used to line fine cotton dresses.




ORGANZA

A pure silk organza makes an excellent interfacing for sheer fabric to give support and structure. It can also be used for structure in much larger areas such as bridal skirts.




NON-WOVEN SEW-IN INTERFACING

A non-woven material is ideal for crafts and small areas of garments, such as cuffs and collars. Use it in garments when a woven or fusible alternative is not available.




HOW TO APPLY A NON-FUSIBLE INTERFACING



1 Place the interfacing on to the wrong side of the fabric, aligning the cut edges.

2 Pin in place.

3 Using a basting stitch, baste the interfacing to the fabric at $\frac{3}{8}$ in (1 cm) within the seam allowance.





PATTERNS

Patterns are available not only for clothes, but for a whole range of crafts and soft furnishing projects. When using a paper pattern to create a garment, you'll need to take your body measurements so that you can compare them to those of the pattern. The pattern may then have to be altered prior to cutting out your fabric. It is always a good idea to test out a pattern in calico before using the real fabric—this is known as making a toile. The toile will help you analyze the fit and whether or not the style chosen suits your figure type. The final step is to pin the pattern on the fabric, cut out the pieces, and transfer all the marks from the pattern to the fabric.

Paper patterns are available for clothing, crafts, and home furnishings. A pattern has three main components: the envelope, the pattern, and the instructions. The envelope gives an illustration of the item that can be made from the contents, together with fabric suggestions and requirements. The pattern sheets inside the envelope are normally printed on tissue and contain a wealth of information, while the instructions tell you how to construct the item.

Reading a pattern envelope

The envelope front illustrates the finished garment or item that can be made from the contents of the envelope. This may be a line drawing or a photograph. The different versions are known as views. On the reverse of the envelope, there is usually an illustration of the back view and the standard body measurement chart that has been used for this pattern, plus a chart that will help you purchase the correct amount of fabric for each view. Suitable fabrics are also suggested alongside “notions,” or haberdashery, which are all the bits and pieces you need to complete the project.

Number of pattern pieces

5678

15 PIECES

Code number for ordering

Description of garment or item, giving details of style and different views included in pattern

MISSES' UNLINED JACKET, SKIRT, SHORTS, AND PANTS.

Unlined, semifitted, V-neck jacket has short sleeves, front buttons, optional waistline darts, and optional breast pocket. Straight skirt, above mid-knee, and pants or shorts with straight legs, have waistband, front pleats, side seam pockets, and back zipper.

List of pattern sizes in imperial and metric measurements for bust, waist, and hips in each size

FABRICS: jacket, skirt, shorts, and pants: wool crepe, soft cottons, sheeting, linen, silk, silk types, and lightweight woolsens. Skirt, shorts, and pants also challis, jacquards, and crepe.

Unsuitable for fabrics printed with obvious diagonals. Allow extra fabric in order to match plaids, stripes, or one-way design fabrics.

Suggested fabrics suitable for garment or item as well as unsuitable fabrics

Use nap yardages/layouts for shaded, pile, or one-way design fabrics.

*with nap, ** without nap

NOTIONS: Thread: three 7/8 in (1.2 cm) buttons; 1/4 in (6 mm) shoulder pads. Skirt, pants: pkg of 1 1/4 in (3.2 cm) waistband interfacing; 7 in (18 cm) zipper; and one hook and eye closure.

Notions required for each view

A

A

B

B

IMPERIAL

Body measurements	(6	8	10)	(12	14	16)	(18	20	22)
Bust	30 1/2	31 1/2	32 1/2	34	36	38	40	42	44 in
Waist	23	24	25	26 1/2	28	30	32	34	37 in
Hip	32 1/2	33 1/2	34 1/2	36	38	40	42	44	46 in

Fabric needed	(6	8	10)	(12	14	16)	(18	20	22)
Jacket	115 cm*/**	1.70	1.70	1.70	1.80	1.80	2.10	2.20	2.20 m
	150 cm*/**	1.30	1.30	1.30	1.40	1.70	1.70	1.80	1.80 m

Interfacing 1 m of 55–90 cm lightweight fusible or non-fusible

Skirt A	115 cm*/**	1.6	1.6	1.6	1.6	1.9	1.9	1.9	2 m
	150 cm*/**	1.2	1.2	1.3	1.3	1.3	1.4	1.4	1.5 m

Shorts B	115 cm*/**	1.6	1.6	1.6	1.6	1.9	1.9	1.9	2 m
	150 cm*/**	1.2	1.2	1.3	1.3	1.3	1.4	1.4	1.5 m

Pants B	115 cm*/**	2.4	2.4	2.4	2.4	2.4	2.4	2.7	2.7 m
	150 cm*	2	2	2	2	2.1	2.1	2.2	2.3 m
	150 cm**	1.6	1.6	1.8	2	2	2.1	2.2	2.3 m

Garment measurements

	(6	8	10)	(12	14	16)	(18	20	22)
Jacket bust	92	94.5	97	101	106	111	116	121	126 cm
Jacket waist	81	83	86	89.5	94.5	100	105	110	116 cm
Jacket back length	73	73.5	74	75	75.5	76	77	77.5	78 cm
Skirt A lower edge	99	101	104	106	112	117	122	127	132 cm
Skirt A length	61	61	61	63	63	63	65	65	65 cm
Shorts B leg width	71	73.5	76	81	86.5	94	99	104	109 cm
Shorts B side length	49.5	50	51	51.5	52	52.5	53.5	54	54.5 cm
Pants B leg width	53.5	53.5	56	56	58.5	58.5	61	61	63.5 cm
Pants B side length	103	103	103	103	103	103	103	103	103 cm

METRIC

Body measurements	(6	8	10)	(12	14	16)	(18	20	22)
Bust	78	80	83	87	92	97	102	107	112 cm
Waist	58	61	63.5	66	71	76	81	86	94 cm
Hip	81	84	86	91	96.5	102	107	112	117 cm

Fabric needed	(6	8	10)	(12	14	16)	(18	20	22)
Jacket	45 in*/**	17/8	17/8	17/8	17/8	2	2 3/8	2 3/8	2 3/8 yd
	60 in*/**	13/8	13/8	13/8	1 1/2	17/8	17/8	17/8	2 yd

Interfacing 1 1/8 yd of 22–36 in lightweight fusible or non-fusible

Skirt A	45 in*/**	13/4	17/8	17/8	17/8	2	2	2	2 1/8 yd
	60 in*/** <td>1 1/4</td> <td>1 1/4</td> <td>1 3/8</td> <td>1 3/8</td> <td>1 3/8</td> <td>1 3/8</td> <td>1 1/2</td> <td>1 5/8 yd</td>	1 1/4	1 1/4	1 3/8	1 3/8	1 3/8	1 3/8	1 1/2	1 5/8 yd

Shorts B	45 in*/**	13/4	13/4	13/4	13/4	2	2	2	2 1/8 yd
	60 in*/** <td>1 1/4</td> <td>1 1/4</td> <td>13/8</td> <td>13/8</td> <td>13/8</td> <td></td>	1 1/4	1 1/4	13/8	13/8	13/8			

Figure shapes

Most people fall into one of these four basic figure shapes. Pattern books and envelopes may feature these symbols and they can be used to help you choose suitable patterns for your figure.



THE WEDGE

Upper body (bust and shoulders) is larger than lower body (hips).



THE RECTANGLE

Upper and lower body are of similar proportions.



THE TRIANGLE

Lower body (hips) is larger than upper body (bust and shoulders).





THE HOURGLASS

Upper and lower body similar in proportion with a small, neat waist.


Single-size patterns

Some patterns contain a garment or craft project of one size only. If you are using a single-size pattern, cut around the tissue on the thick black cutting line before making any alterations.




Multi-size patterns

Many patterns today have more than one size printed on the tissue. Each size is clearly labeled and the cutting lines are marked with a different type of line for each size.



Pattern markings

Each pattern piece will have a series of lines, dots, and other symbols printed on it. These symbols are to help you alter the pattern and join the pattern pieces together. The symbols are universal across all major paper patterns.



BODY MEASURING

TAKING BODY MEASUREMENTS

You'll need a tape measure and ruler as well as a helper for some of the measuring, and a hard chair or stool.

Wear close-fitting clothes such as a leotard and leggings.

Do not wear any shoes.

HOW TO MEASURE YOUR HEIGHT

Most paper patterns are designed for a woman 5 ft 5 in to 5 ft 6 in (165 to 168 cm). If you are shorter or taller than this you may need to adjust the pattern prior to cutting out your fabric.

- 1** Remove your shoes.
- 2** Stand straight, with your back against the wall.
- 3** Place a ruler flat on your head, touching the wall, and mark the wall at this point.
- 4** Step away and measure the distance from the floor to the marked point.

Accurate body measurements are needed to determine the correct pattern size to use and if any alterations are required. Pattern sizes are usually chosen by the hip or bust measurement; for tops follow the bust measurement, but for skirts or pants use the hip measurement. If you are choosing a dress pattern, go by whichever measurement is the largest.

Chest

Measure above the bust, high under the arms, keeping the tape measure flat and straight across the back.



Full bust

Make sure you are wearing a good-fitting bra and measure over the fullest part of the bust. If your cup size is in excess of a B, you will probably need to do a bust alteration, although some patterns are now cut to accommodate larger cup sizes.



Waist

This is the measurement around the smallest part of your waist. Wrap the tape around first to find your natural waist, then measure.



Hips

This measurement must be taken around the fullest part of the hips, between the waist and legs.




High hip

Take this just below the waist and just above the hip bones to give a measurement across the tummy.



Shoulder

Hold the end of the tape measure at the base of your neck (where a necklace would lie) and measure to the dent at the end of your shoulder. To find this dent raise your arm slightly.



Neck

Measure around the neck—snugly but not too tight—to determine collar size.




Arm

Bend your elbow and place your hand on your hip, then measure from the end of the shoulder over the elbow to the wrist bone.



Back waist

Take this measurement down the center of the back, from the lumpy bit at the top of the spine, in line with the shoulders, to the waist.




Outside leg

Measure the side of the leg from the waist, over the hip, and straight down the leg to the ankle bone.



Inside leg

Stand with your legs apart and measure the inside of one leg from the crotch to the ankle bone.



Crotch depth

Sit upright on a hard chair or stool and measure from the waist vertically down to the chair.



ALTERING PATTERNS

It is unlikely that your body measurements will be exactly the same as those of your chosen pattern, so you will need to alter the pattern to accommodate your figure. Here is how to lengthen and shorten pattern pieces, and how to make specific alterations at the bust, waist and hips, shoulders and back, and to sleeves and pants.

Equipment

In addition to scissors and pins or tape, you will need a pencil, an eraser, a ruler that is clearly marked, and possibly a set square. For many alterations, you will also need pattern paper. After pinning or taping the piece of pattern tissue to the paper, you can redraw the pattern lines. Trim away the excess tissue or paper before pinning the pattern pieces to the fabric for cutting out.

Easy multi-size pattern alterations

Using a multi-size pattern has many advantages, as you can cut it to suit your unique individual shape—for example, to accommodate a hip measurement that may be two sizes different to a waist measurement, or your not being precisely one size or another.

INDIVIDUAL PATTERN ADJUSTMENT

To adjust for a wider hip measurement, when cutting from one size to another, make the lines a gentle curve to follow the contours of the body.



BETWEEN SIZES

If your body measurements fall between two pattern sizes, cut carefully between the two cutting lines for the different sizes.



Lengthening and shortening patterns


If you are shorter or taller, or your arms or legs are shorter or longer, than the pattern pieces, you will need to adjust the paper pattern prior to cutting out. There are lines printed on the pattern pieces that will guide you as to the best places to adjust. However, you will need to compare your body shape against the pattern. Alter the front and back by the same amount at the same points, and always check finished lengths.

FOR A FITTED SLEEVE

On sleeve with elbow shaping, alter by half required amount halfway between elbow and underarm


Elbow shaping

Alter by other half of required amount halfway between elbow and wrist



FOR A STRAIGHT SLEEVE

To keep wrist area intact, alter partway down sleeve, or at hem




FOR A BODICE

Alter back neck to waist length below bust dart but above waist (through waist dart if there is one)


Bust dart

Waist


Waist dart




FOR A FITTED DRESS




FOR A PRINCESS DRESS




FOR SHORTS




FOR A SKIRT





FOR SHAPED-LEG PANTS




FOR STRAIGHT PANTS




HOW TO LENGTHEN A PATTERN PIECE



HOW TO SHORTEN A PATTERN PIECE



1 Work out the amount you want to lose. Mark this amount above the lengthening and shortening lines, then draw a line through the marks using the ruler as a guide.




2 Fold the lengthening and shortening line on to the drawn line so the two lines meet neatly.




3 Press with your fingers to crease the fold sharply, then secure the fold in the pattern piece with tape.


HOW TO LENGTHEN ACROSS DARTS




HOW TO SHORTEN ACROSS DARTS



HOW TO LENGTHEN A HEM EDGE



HOW TO SHORTEN A HEM EDGE



Bust


Some paper patterns today feature various cup sizes, but the majority of patterns are cut to accommodate a B cup. If you are larger than this, you will probably need to adjust your pattern before cutting out. As a general rule, when spreading the pattern pieces apart, try adjusting by $\frac{1}{4}$ in (6 mm) per cup size over a B cup. Other pattern alterations can be made for bust position, raising it higher or lowering it. If the bust dart is altered, the waist dart may also need to be adjusted.

RAISING A BUST DART

- 1 If you have a high bust, you may need to raise the point of the darts. The bust point is nearly always marked on the pattern pieces. Mark the new bust point on the tissue.

- 2 Redraw the lines of the dart to this point.

Lengthened waist dart




RAISING A BUST DART SUBSTANTIALLY

- 1 If the dart has to be raised quite a lot, it is easier to cut a rectangle out of the part of the pattern that contains the dart and then move it higher.

- 2 Mark the new bust point on the tissue first.

- 3 Use a sheet of pattern paper to fill in the gap and tape in place.

Raised waist dart




INCREASING A BUST DART

- 1 Cut the pattern as indicated, straight through the bust point.

- 3 Tape securely in place.

- 2 Place the tissue pieces on pattern paper, then spread them apart by $\frac{1}{4}$ in (6 mm) per cup size over a B cup.

Dart redrawn to original length




LOWERING A BUST DART

- 1 Mark the new lower bust point on your pattern piece.

- 2 Redraw the dart stitching lines to this new lower point.

Shortened waist dart




LOWERING A BUST DART SUBSTANTIALLY

- 1 First mark the new bust point on the tissue.

- 2 Cut out a rectangle from the pattern piece that contains the dart and move it to the lower position.

- 3 Fill in the gap with a sheet of pattern paper and tape in place.

Lowered waist dart




INCREASING A FRENCH DART

- 1 Cut the pattern piece along the dart line from the side seam, straight through the bust point to the center front line.

- 2 Spread the tissue apart and tape to pattern paper.


- 3 Mark a new dart point in the center of where the dart has been spread.

- 4 Redraw the dart from the original seam points.



RAISING A CURVED BUST SEAM

- 1** Fold a pleat in the shoulder pattern to bring the bust point up by the required amount.




- 2** Cut the pattern on the lengthening and shortening lines and spread apart by the same amount (if this is not done, the waist will be raised as well).

- 3** Tape the pieces to pattern paper, then redraw the armhole lower by the same measurement.

LOWERING A CURVED BUST SEAM

- 1** Cut the shoulder pattern piece and spread apart by the required amount, then tape to a sheet of pattern paper.




- 2** Make a fold on the lengthening and shortening lines by the same amount.

- 3** Redraw the armhole higher by the same amount.

ADJUSTING A CURVED SEAM

- 1** For a larger bust, place a sheet of pattern paper under the tissue pieces in the bust area.



- 2** Add the required amount to each piece, remembering to split it between them equally—if you need to increase by $\frac{1}{2}$ in (1.2 cm), add $\frac{1}{4}$ in (6 mm) on to each piece.

- 3** Redraw the curves on the paper back into the seam line.

Waist and hips


Most people's waists and hips are out of proportion when compared to the measurements of a paper pattern. To alter the pattern to suit your body shape, adjust the pieces for the waist first and then do the hip pieces.

INCREASING THE WAIST AT A SEAM

- 1** On a fitted skirt, increase the waist at the side seams. Divide the amount to be increased by four as there are four seamlines.

- 2** Tape pattern paper behind the tissue pieces and add the increase on at the waist edge.


- 3** Draw a new seamline from this point, tapering it back into the skirt side seam.



INCREASING THE WAIST ON A GORED SKIRT


- 1** As there are many seams on a gored skirt, divide the increase amount by the number of seamlines.

- 2** Tape the tissue pieces on to pattern paper and add one of these small amounts to each seamline at the waist.



INCREASING THE WAIST ON A FULL-CIRCLE SKIRT

1 First carefully check the waist circumference on the pattern against your body measurements.




2 Make the waist larger by drawing a new, lower waist stitching line on the pattern pieces.

3 Be sure to adjust the finished length of the skirt, if necessary.

INCREASING THE WAIST ON A FITTED DRESS

1 Place a sheet of pattern paper under the side seam section of each of the pattern pieces.




2 Add one-quarter of the total increase, redrawing the waist curve to straighten it.

3 If more increase is required, the darts can be made narrower as well.

INCREASING THE WAIST ON A PRINCESS-LINE DRESS

1 Place a sheet of pattern paper under the waist section of each of the pattern pieces.




2 Divide the amount to be increased by the number of seamlines.

3 Add one of these smaller amounts on to each seamline.

DECREASING THE WAIST AT A SEAM

1 On a straight skirt, divide the amount to be decreased by four as there are four seamlines.




2 Mark the amount of decrease at the waist edge on the pattern pieces.

3 Redraw the side seams, tapering back into the pattern line.

DECREASING THE WAIST ON A GORED SKIRT


1 Divide the amount to be decreased by the number of seamlines.



2 Take one of these small amounts off each seamline at the waist.

DECREASING THE WAIST ON A FULL-CIRCLE SKIRT

1 Tape the pattern tissue to a sheet of pattern paper.




2 Draw the stitching line at the waist higher, which will make the waist smaller.

DECREASING THE WAIST ON A FITTED DRESS

1 To reduce the waist seam, you need to redraw the side seamline on each pattern piece. Divide the total decrease by four.

2 Measure one-quarter of the total amount to be decreased at the waist.


3 Draw a curved line from above and below to this point.



DECREASING THE WAIST ON A PRINCESS-LINE DRESS

1 Divide the total amount of reduction by the number of seamlines, then mark the required amount of decrease at the waist on each pattern piece.

2 Redraw the seams, curving each one in to the marked point.




WIDENING A FITTED SKIRT AT THE HIPLINE

1 To increase the hip dimension on a fitted skirt, divide the amount of the increase by four. Place the tissue pieces on pattern paper and increase each side seam at the hip point by the required amount.

2 Redraw the seamline from the hip increase, gradually tapering into the waistline.

3 It is more flattering to take the adjustment all the way down the skirt, so redraw the seamline straight down from the hip to the hem.




ADJUSTING A FITTED SKIRT FOR EXTRA-LARGE HIPS

1 For an increase over 2 in (5 cm), cut each pattern piece vertically between the dart and the side seam.

2 Place on pattern paper and spread apart by one-quarter of the total amount of increase.


3 If the waist is to remain the same, draw in a second dart to remove the increase at the waist.



ADJUSTING A FITTED SKIRT FOR PROMINENT HIPS

1 Place the tissue on pattern paper and add the required amount from the waist to the hip point as for a fitted skirt (see left), tapering the line back into the seam.

2 Increase the width of the dart by the same amount, redrawing the dart lines to the new center point.




ADJUSTING A FITTED SKIRT FOR A LARGE BOTTOM

1 Cut through the skirt back pattern piece, vertically through the dart to the hem.

2 Cut across the hipline, but not through the side seam.

3 Spread apart the tissue on pattern paper as much as needed and tape in place.


4 Redraw the dart.



DECREASING THE HIPLINE ON A FITTED SKIRT

1 Divide the amount to be reduced by four and mark the reduction amount on each pattern piece at the hipline.

2 Redraw the side seam, tapering the line into the waist and from the hipline, drawing straight down to the hem.




ADJUSTING THE HIPLINE ON A GORED SKIRT OR PRINCESS DRESS

1 Divide the amount to be reduced or added by the number of seamlines.

2 If widening, tape the pieces of tissue to pattern paper.

3 Mark the reduction or addition at the hipline on each piece.

4 Redraw the seamlines, tapering them into the waist and drawing straight down to the hem.




MAKING A LARGE INCREASE AT THE HIPLINE ON A FITTED DRESS

1 Make a cut into each pattern piece horizontally just below the waist by one-quarter of the total amount to be increased.

2 Cut vertically to the hem.

3 Spread the tissue apart and tape to a sheet of pattern paper.


4 Redraw the side seam.



ADJUSTING AT THE HIPLINE TO ALLOW FOR A HOLLOW BACK

1 A hollow back requires a shorter center back seam. Draw a line on the pattern piece across the hipline, from the center back.


2 Fold along the line to make a pleat of the required reduction, tapering it to nothing at the side seam. Tape in place.




Shoulders, back, and sleeves

Alterations can be made to accommodate sloping shoulders, square shoulders, and backs that may be wider or narrower than the pattern allowances. It's important to ensure that these alterations have a minimum effect on the armhole. Sleeves need to allow for movement, so should not be too tight, and pattern pieces can be enlarged as necessary. Alterations can also be made for thin arms.


ADJUSTING TO FIT SQUARE SHOULDERS

- 1 Starting at the armhole, slash the pattern piece about $1\frac{1}{4}$ in (3 cm) below and parallel with the shoulder line, not cutting through the neck seamline.
 - 2 Spread the tissue apart to make the shoulder line straighter. Tape to pattern paper.
 - 3 Redraw the line across the gap created.
 - 4 Raise the armhole by the amount added at the shoulder.
- 


ADJUSTING TO FIT SLOPING SHOULDERS

- 1 Slash from the armhole across the pattern piece $1\frac{1}{4}$ in (3 cm) below the shoulder line and parallel with it.
 - 2 Overlap the tissue by the required amount and tape in place.
 - 3 Lower the armhole by the same amount, drawing a new seamline on the tissue.
- 


PREPARING THE PATTERN FOR BROAD OR NARROW SHOULDER ALTERATIONS

- 1 Draw a vertical line 8 in (20 cm) long from the middle of the shoulder line.
 - 2 Next, draw a second line horizontally from the end of this line to the armhole.
- 

ADJUSTING TO FIT BROAD SHOULDERS


- 1 Cut along the lines that have been drawn and spread the pieces of tissue apart on pattern paper, to accommodate the increase in shoulder length.
 - 2 Tape in place and redraw the shoulder line.
- 

ADJUSTING TO FIT NARROW SHOULDERS

- 1 Cut along the drawn lines.
 - 2 Slide the cut-out piece of tissue in to overlap the cut edges and reduce the shoulder length.
 - 3 Tape on to pattern paper and redraw the shoulder line.
- 

ENLARGING A FITTED SLEEVE


- 1 Cut the sleeve pattern piece vertically down the center.



- 2 Spread apart as much as required to make the sleeve wider. Tape to pattern paper.

ENLARGING THE HEAD ON A FITTED SLEEVE

- 1 Cut the pattern piece vertically down the center, not cutting through the wrist seamline.




- 2 Spread the tissue apart at the top by the required amount and taper to nothing at the wrist.

- 3 You may need to make the armhole slightly larger, by adding half this amount to each bodice side seam.

ENLARGING A FITTED SLEEVE AT THE ELBOW

- 1 Cut horizontally at an angle from just above the elbow dart to the center, then cut vertically almost to the top.




- 2 Spread the tissue on pattern paper, leaving the sleeve head intact, and tape to the paper.

- 3 Redraw the underarm seam over the gap created.

INCREASING AT THE UNDERARM ON A FITTED SLEEVE

- 1 If the underarm is tight, cut the pattern horizontally from armhole to armhole, then cut the top piece of tissue vertically almost to the sleeve head.



- 2 Pull the outside points up to make a gap in the center of the required amount, and tape to pattern paper.


- 3 Redraw the sleeve side seams.

DECREASING A FITTED SLEEVE FOR THIN ARMS

- 1 To decrease the width of a sleeve, make a vertical pleat in the center of the sleeve pattern piece, from wrist to sleeve head.

- 2 Taper the pleat to nothing at the sleeve head. Tape in place.

- 3 Reduce the side seams on the armhole by half this amount.



Pants


Pant alterations, to accommodate a large stomach, wide hips, or a prominent or flat bottom, can be more complicated than those on other pattern pieces, and need to be done in the correct order. Crotch depth alterations are done first, followed by width alterations, then crotch length alterations, and finally pant leg length. The crotch depth line is only marked on the back pattern pieces.

INCREASING DEPTH AT CROTCH SEAM

1 Adjust both back and front pattern pieces by the same amount. Cut along the upper lengthening and shortening lines.

2 Spread the pattern tissue apart by the required amount at the center back and center front seams, tapering to nothing at the side seam. Tape the tissue to pattern paper.


3 Redraw the crotch edge.



DECREASING DEPTH AT CROTCH SEAM

1 Adjust both back and front pattern pieces by the same amount. Cut each of the pattern pieces along the lengthening and shortening lines.


2 Overlap by the amount to be reduced, working from the center and tapering to nothing at the side seam.



INCREASING THE WAISTLINE

1 Divide the amount to be increased by eight (there are eight seamlines that you can add on to). Tape the tissue to pattern paper.

2 Add an equal amount to each seamline at the waist, tapering the new drawn line back into the seam.




DECREASING THE WAISTLINE

1 Take the amount to be decreased and divide it by eight.

2 Reduce each of the waist seamlines by this amount.

3 Draw a new line from the decrease point back into the seamline on the pattern.




INCREASING AT THE HIPLINE

1 Take the amount to be increased and divide it by four.

2 Place a sheet of pattern paper under the hip area on the side seam of each pattern piece.

3 Add the required amount to each of the seamlines at the hip, tapering the new seamline into the waist and thigh.

4 For straight pants, draw the new seamline straight down from the hip to the hem.




ADJUSTING FOR A LARGE BOTTOM

1 Cut through the pant back pattern pieces at the hipline.

2 Place the tissue on pattern paper and spread apart by the required amount, then tape the tissue to the paper.

3 Redraw the crotch edge. This adjustment may be in addition to a crotch depth adjustment.




DECREASING AT THE HIPLINE

1 For fitted pants, divide the amount to be decreased by four.

2 Reduce the side seam at the hipline on each pattern piece by one-quarter of the total reduction.


3 Taper the new drawn seamline to waist and thigh.



INCREASING LENGTH AT CROTCH POINT

1 The crotch length may need to be increased by a different amount on the front and back. Tape a sheet of pattern paper under the crotch seam.


2 Add on the amount required and redraw the inside leg seam from this new crotch point, tapering into the original seamline.



DECREASING LENGTH AT CROTCH POINT

1 To reduce the length of the crotch seam, make a mark on the pattern piece where the new crotch point should be.

2 Redraw the inside leg seam from this point to taper into the original seamline.



MAKING A TOILE

When using a new pattern for the first time, or if you have made pattern alterations, it is always a good idea to try out the pattern in calico, to make a test garment called a toile. This will tell you if the garment is going to fit you, or whether more alterations are required. It is also a good opportunity to confirm that the style suits your figure type. You will need a helper, or failing that, a dressmaker's dummy.

Toile too big

When you try the toile on, if it is too big there will be surplus fabric. Pleat and pin out the surplus fabric, making the pleating equal on both the left and right-hand sides of the garment. Take off the toile and measure the surplus amount. Alter the pattern pieces to match, by pinning out the surplus tissue.

BACK ADJUSTMENT

If the back is too big, pleat and pin out the surplus fabric parallel to the center back seam, doing this equally on both sides. The alteration can then be made down the center back seam on the appropriate pattern pieces.




THE WAIST ON THE BODICE AND SKIRT

If the waist is too big, this can easily be adjusted by taking more fabric into the bust dart, thus making the waist smaller. If you adjust the bust dart on the bodice, you will need to alter the skirt dart too, so they join up.

THE HIP ON THE SKIRT

If the hip is too loose, pleat and pin out the surplus fabric, doing this equally on both side seams. Measure the surplus amount and take in the hipline on the pattern pieces accordingly (see Decreasing the hipline on a fitted skirt, page 69).



SHOULDER ADJUSTMENT

If the shoulder is too wide it will need a sloping shoulder adjustment (see page 70).

Toile too small

If the toile is too small, the fabric will “pull” where it is too tight. The garment shown below is too tight over the bust and also over the high hip area. The pattern will need adjusting to allow more fabric in these areas. It is also snug at the top of the sleeve, which will need adjusting.

THE BUST ON THE BODICE

If a small increase is required in the bust, unpick the side seams and measure the increase required. Then make the required alteration to the pattern pieces. If a larger increase is required the whole pattern piece will need to be altered and a new front cut out (see Increasing a bust dart, page 65). To be sure the alteration is successful, make up a new toile bodice to try.

SHOULDER ADJUSTMENT

If the sleeve is tight at the top, or at the underarm, it is best to alter the pattern pieces (see page 71) and then to make up a new sleeve for the toile.

HOW TO ADJUST A TOILE THAT IS TOO SMALL

If the toile is too tight, it will require more fabric to cover the contours of the body and you will need to make further alterations to the pattern pieces. For small increases (up to 1½ in/4 cm), you can adjust the toile as described below and then alter the pattern pieces accordingly, redrawing the seamlines. For more substantial increases, after altering the pattern pieces you will need to make up a new toile to try on.

1 Where the toile is too tight, unpick the side seam on either side, until the garment will hang without pulling.

2 Measure the gap between the stitching lines where the seam has been opened at the fullest point. It should be the same on both sides of the body.

3 Divide this measurement in half—for example, if the gap is 1½ in (4 cm) at the fullest point, then ¾ in (2 cm) needs to be added to each seamline.

4 Using a marker, mark directly on the toile the top and bottom of the alteration. Also mark the fullest point of the alteration.

5 When the toile has been removed, add muslin to the seam in the given area at the fullest point, tapering back to the original seam at either end.

6 Try the toile on again to be sure your alterations have made it fit you properly, then measure them and make adjustments to the relevant pattern pieces.

THE HIP ON THE SKIRT

Unpick the side seams and measure the increase required. When you have adjusted the toile with extra calico to be sure the fit is right, you can alter the pattern pieces accordingly (see page 68).



CUTTING OUT

Cutting out correctly can make or break your project. But first you need to examine the fabric in the store, looking for any flaws, such as a crooked pattern, and checking to see if the fabric has been cut properly from the roll—that is at a right angle to the selvage. If not you will need to straighten the edge. If the fabric is creased, press it; if washable, wash it to avoid shrinkage later. After this preparation, you will be ready to lay the pattern pieces on the fabric, pin in place, and cut out.


Fabric grain and nap

It is important that the pattern pieces are cut on the correct grain, as this will make the fabric hang correctly and produce a longer-lasting item. The grain of the fabric is the direction in which the yarns or threads that make up the fabric lie. The majority of pattern pieces need to be placed with the straight of grain symbol running parallel to the warp yarn. Some fabrics have a nap due to the pile, which means the fabric shadows when it is smoothed in one direction. A fabric with a one-way design or uneven stripes is also described as being with nap. Fabrics with nap are generally cut out with the nap running down, whereas those without nap can be cut out at any angle.

GRAIN ON WOVEN FABRICS

The selvage is the woven, non-frayable edge that runs parallel to the warp grain.


Weft yarns run crosswise, over and under the warp yarns.



Yarns that run the length of the fabric are called warp yarns. They are stronger than weft yarns and less likely to stretch.

The bias grain is diagonal—running at 45 degrees to the warp and weft. A garment cut on the bias will follow the contours of the body.

GRAIN ON KNITTED FABRICS



A knitted fabric also has a grain. Some knit fabrics stretch only one way while others stretch in both directions. Patterns for knit fabrics often need to be cut following the direction of the greatest stretch.

NAP DUE TO PILE



Fabrics such as velvet, corduroy, and velour will show a difference in color, depending on whether the nap is running up or down.

NAP IF ONE-WAY DESIGN



A one-way pattern—in this case flowers—that runs lengthwise in the fabric will be upside-down on one side when the fabric is folded back on itself.

NAP IF STRIPED





If the stripes do not match on both sides when the fabric is folded back, they are uneven and the fabric will need a nap layout.

Fabric preparation

To check if the fabric has been cut properly from the roll, smooth it out flat, with the selvages lying together. If the cut ends are uneven and do not match, use one of the following methods to make the edge straight. Then press the fabric.

PULLING A THREAD TO OBTAIN A STRAIGHT EDGE




CUTTING ON A STRIPE LINE



On plaid and stripes, cut along the edge of one of the boldest stripes to achieve a straight edge.


CUTTING ON A STITCH LINE ON KNIT FABRICS




On jersey and other knit fabrics, if you look carefully, you can cut along a row of stitches.

Pattern preparation

Before cutting out, sort out all the pattern pieces that are required for the item you are making. Check them to see if any have special cutting instructions. Make pattern alterations, if necessary. If there are no alterations, just trim patterns to your size.



1 Using the pattern instruction sheet, which has drawings of the pattern pieces, select the pieces you require.



2 The instruction sheet also shows a suggested cutting-out layout for the item you are making, on different widths of fabric, with or without nap.




3 Trim multi-size pattern pieces according to the chosen size. Single-size pattern pieces do not need to be cut to shape; just cut around them roughly if there is excess tissue.


Pattern layout

Fabric is usually folded selvage to selvage. With the fabric folded, the pattern is pinned on top, and both the right and left side pieces are cut at the same time. If pattern pieces have to be cut from single layer fabric, remember to cut matching pairs. For a fabric with a design, it is a good idea to have this on the outside so that you can arrange the pattern pieces to show off the design. If you have left and right side pattern pieces, they are cut on single fabric with the fabric right side up and the pattern pieces right side up.


PINNING THE PATTERN TO THE FABRIC




GENERAL GUIDE TO LAYOUT




LAYOUT FOR FABRICS WITH A NAP OR A ONE-WAY DESIGN




LAYOUT ON A CROSSWISE FOLD



LAYOUT ON A CROSSWISE FOLD WITH A NAP



LAYOUT ON A PARTIAL FOLD



Stripes and plaid

For fabrics with a stripe or plaid pattern, a little more care is needed when laying out the pattern pieces. If the checks and plaid are running across or down the length of the fabric when cutting out, they will run the same direction in the finished garment. So it is important to place the pattern pieces to ensure that the plaid and stripes match and that they run together at the seams. If possible, try to place the pattern pieces so each has a stripe down the center. With plaid, be aware of the hemline placement on the pattern.

EVEN OR UNEVEN STRIPES

EVEN STRIPES



When a corner of the fabric is folded back diagonally, the stripes will meet up at the fold.


UNEVEN STRIPES



When a corner of the fabric is folded back diagonally, the stripes will not match at the fold.

EVEN OR UNEVEN PLAID

EVEN PLAID



When a corner is folded back diagonally, the plaid will be symmetrical on both of the fabric areas.

UNEVEN PLAID



When a corner of the fabric is folded back diagonally, the plaid will be uneven lengthwise, widthwise, or both.

MATCHING STRIPES OR PLAID ON A SKIRT


1 Place one of the skirt pattern pieces on the fabric and pin in place.

2 Mark on the tissue the position of the boldest lines of the plaid or stripes.



3 Place the adjoining skirt pattern piece alongside, with notches matching and side seams even. Transfer the marks across.

4 Move the second pattern piece away, matching up the bold lines, and pin it in place.



MATCHING STRIPES OR PLAID AT THE SHOULDER


1 Mark the boldest lines of the stripes or plaid around the armhole on the front bodice pattern.

2 Place the sleeve pattern on to the armhole, matching the notches, and copy the marks on to the sleeve pattern.


3 Place the sleeve pattern on to the fabric, matching the marks to the corresponding bold lines, and pin in place.




LAYOUT FOR EVEN PLAID ON FOLDED FABRIC



LAYOUT FOR EVEN STRIPES ON FOLDED FABRIC



LAYOUT FOR UNEVEN PLAID OR STRIPES ON UNFOLDED FABRIC



Cutting out accurately

Careful, smooth cutting around the pattern pieces will ensure that they join together accurately. Always cut out on a smooth, flat surface such as a table—the floor is not ideal—and be sure your scissors are sharp. Use the full blade of the scissors on long, straight edges, sliding the blades along the fabric; use smaller cuts around curves. Do not nibble or snip at the fabric.


HOW TO CUT



If you are right-handed, place your left hand on the pattern and fabric to hold them in place, and cut cleanly with the scissor blades at a right angle to the fabric.


MARKING NOTCHES

These symbols need to be marked on to the fabric as they are matching points. One of the easiest ways to do this is to cut the mirror image of the notches out into the fabric. Rather than cutting out each notch separately, cut straight across from point to point.




MARKING DOTS

You can cut a small clip into the fabric to mark the dots that indicate the top of the shoulder on a sleeve. Alternatively, these can be marked with tailor's tacks (see opposite page).



CLIPPING LINES


A small clip or snip into the fabric is a useful way to mark some of the lines that appear on a pattern, such as the center front line and foldlines.



Pattern marking

Once the pattern pieces have been cut out, you will need to mark the symbols shown on the tissue through to the fabric. There are various methods to do this. Tailor's tacks are good for circles and dots, or mark these with a water or air-soluble pen (when using a pen, it's a good idea to test it on a piece of scrap fabric first). For lines, you can use trace basting or a tracing wheel with dressmaker's carbon paper.

TRACE BASTING



1 This is a really useful technique to mark center front lines, foldlines, and placement lines. With double thread in your needle, stitch a row of loopy stitches, sewing along the line marked on the pattern.




2 Carefully pull away the tissue. Cut through the loops, then gently separate the layers of fabric to show the threads. Snip apart to leave thread tails in both of the fabric layers.


TAILOR'S TACKS

1 As there are often dots of different sizes, it is a good idea to choose a different color thread for each dot size. It is then easy to match the colors as well as the dots. Have double thread in your needle, unknotted. Insert the needle through the dot from right to left, leaving a tail of thread. Be sure to go through the tissue and both layers of fabric.


2 Now stitch through the dot again, this time from top to bottom to make a loop. Cut through the loop, then snip off excess thread to leave a tail.



3 Carefully pull the pattern tissue away. On the top side, you will have four threads marking each dot. When you turn the fabric over, the dot positions will be marked with an X.




4 Gently turn back the two layers of fabric to separate them, then cut through the threads so that thread tails are left in both pieces of fabric.



TRACING PAPER AND WHEEL

1 This method is not suitable for all fabrics as the marks may not be able to be removed easily. Slide dressmaker's carbon paper against the wrong side of the fabric.


2 Run a tracing wheel along the pattern lines (a ruler will help you make straight lines).



3 Remove the carbon paper and carefully pull off the pattern tissue. You will have dotted lines marked on your fabric.




MARKERS

1 This method can only be used with a single layer of fabric. Press the point of the pen into the center of the dot marked on the pattern piece.



2 Carefully remove the pattern. The pen marks will have gone through the tissue on to the fabric. Be sure not to press the fabric before the pen marks are removed or they may become permanent.

TECHNIQUES





STITCH ESSENTIALS

Seams and stitches are the essential construction elements of your work. Some stitches are created by hand, while others are made on the sewing machine or serger.


STITCHES FOR HAND SEWING

HOW TO THREAD A NEEDLE


When sewing by hand, cut your piece of thread to be no longer than the distance from your fingertips to your elbow. If the thread is much longer than this, it will knot as you sew.

- 1 Hold your needle in your right hand and the end of the thread in your left. Keeping the thread still, place the eye of the needle over the thread.
- 2 If the needle will not slip over the thread, dampen your fingers and run the moisture across the eye of the needle.
- 3 Pull the thread through the eye of the needle.
- 4 At the other end of the thread, tie a knot as shown below or secure the thread as shown right.


Threading the needle




Slip the eye of the needle over the thread.



Pull the thread through.



Tie a knot at one end.



You're now ready to sew.


Although modern sewing machines have eliminated the need for a lot of hand sewing, it is still necessary to use hand stitching to prepare the fabric prior to permanent stitching—these temporary pattern marking and basting stitches will eventually be removed. Permanent hand stitching is used to finish a garment and to attach fasteners, as well as to help out with a quick repair.

Securing the thread

The ends of the thread must be secured firmly, especially if the hand stitching is to be permanent. A knot (see left) is frequently used and is the preferred choice for temporary stitches. For permanent stitching, a double stitch is a better option.

DOUBLE STITCH

- 1 Take a stitch.
- 2 Go back through the stitch with the thread wrapped under the needle.
- 3 Pull through to make a knot.




BACK STITCH

Make two small stitches in the same place.



LOCKING STITCH


Start the stitching with a knot (see left).




Basting stitches

Each of the many types of basting stitches has its own individual use. Trace bastes are used to transfer pattern markings to fabric. Basic bastes and bar bastes hold two or more pieces of fabric together. Long and short bastes are an alternative version of the basic basting stitch, often used when the basting will stay in the work for some time. Thread chain bastes work in a similar way to bar bastes but are much finer as they are made by looping a single thread through itself. Diagonal bastes hold folds or overlaid fabrics together, while slip bastes are used to hold a fold in fabric to another piece of fabric.


BASIC BASTES




DIAGONAL BASTES





SLIP BASTES







LONG AND SHORT BASTES



BAR BASTES



THREAD CHAIN BASTES




Hand stitches

There are a number of hand stitches that can be used during construction of a garment or other item. Some are for decorative purposes while others are more functional.


BACK STITCH

A strong stitch that could be used to construct a piece of work. Work from right to left. Bring the needle up, leaving a space, and then take the thread back to the end of the last stitch.




RUNNING STITCH

Very similar to basting (see page 89), but used more for decorative purposes. Work from right to left. Run the needle in and out of the fabric to create even stitches and spaces.




PRICK STITCH

Often used to highlight the edge of a completed garment, such as a collar. Work from right to left. Make small stitches about $\frac{1}{16}$ in (2 mm) long, with spaces between of at least three times that length.




WHIP STITCH

A diagonal stitch sewn with a single thread along a raw edge to prevent fraying. Work from right to left. Take a stitch through the edge of the fabric. The depth of the stitch depends on the thickness of the fabric—for a thin fabric, take a shallow stitch. As a rule, stitch depth should be 0.2 mm at the minimum, 0.5 mm at the maximum.




HERRINGBONE STITCH

A very useful stitch as it is secure yet has some movement in it. It is used to secure hems and interlinings. Work from left to right. Take a small (not more than 0.5 mm) horizontal stitch into one layer and then the other, so the thread crosses itself.




FLAT FELL STITCH

A strong, secure stitch to hold two layers permanently together. This stitch is often used to secure bias bindings and linings. Work from right to left. Make a short, straight stitch at the edge of the fabric.




SLIP HEM STITCH

Also called a catch stitch, this is used primarily for securing hems. It looks similar to herringbone (above). Work from right to left. Take a short horizontal stitch into one layer and then the other.




BLIND HEM STITCH


As the name suggests this is for hemming a garment. As the stitch is under the edge of the fabric it should be discreet. Work from right to left and use a slip hem stitch (left).



BUTTONHOLE STITCH



1 Used to make hand-worked buttonholes and also to secure fastenings. It is always stitched on an edge with no spaces between the stitches. Work from right to left. Push the needle from the top edge into the fabric.



2 Wrap the thread behind the needle as the needle goes in and again as the needle leaves the fabric. Pull through and a knot will appear at the edge. This is an essential stitch for all sewers and is not difficult to master.


BLANKET STITCH

Similar to buttonhole stitch (above) but without the knot. Blanket stitch is useful to neaten edges and for decorative purposes. Always leave a space between the stitches. Push the needle into the fabric and, as it appears at the edge, wrap the thread under the needle.



CROSS STITCH

A temporary securing stitch used to hold pleats in place after construction. It can also be used to secure linings. Work a row of even diagonal stitches in one direction and then a row back over them to make crosses.




Hand-stitched arrowheads

LEVEL OF DIFFICULTY ****


An arrowhead is a triangular shape made by working straight stitches in a set order. This is a permanent stitch placed at an area of strain or stress, such as the top of a split.

1 Mark a triangle on the fabric, with sides about 0.8 mm each. Start with a knot. Bring the needle up through 1 and down through 2.



2 Then bring the needle up through 3 and down through 4. Repeat the stitch.

3 Continue the stitches, up through 5 and down through 6, up through 7 and down through 8.



4 Make about 10 alternating stitches to complete the arrowhead.




MACHINE STITCHES AND SEAMS

Fabric is joined together using seams—whether it be for an item of clothing, craft work, or soft furnishings. The most common seam is a plain seam, which is suitable for a wide variety of fabrics and items. However, there are many other seams to be used as appropriate, depending on the fabric and item being constructed. Some seams are decorative and can add detail to structured garments.

Securing the thread

Machine stitches need to be secured at the end of a seam to prevent them from coming undone. This can be done by hand, tying the ends of the thread, or using the machine with a reverse stitch or a locking stitch, which stitches three or four stitches in the same place.

TIE THE ENDS



1 Pull on the top thread and it will pull up a loop—this is the bobbin thread.

2 Pull the loop through to the top.

3 Tie the two threads together.

REVERSE STITCH

1 When starting, stitch a couple of stitches forward, then hold in the reverse button and reverse over them. Continue forward again.

2 At the end of the seam, reverse again to secure the stitches.

LOCKING STITCH

1 When starting, press the locking stitch and stitch, then continue forward.

2 At the end of the seam, press the locking stitch again.

Stitches made with a machine


The sewing machine will stitch plain seams and decorative seams as well as buttonholes of various styles. The length and width of all buttonholes can be altered to suit the garment or craft item.

STRAIGHT STITCH




Used for most applications. The length of the stitch can be altered from 0.5 to 5.0 on most sewing machines.

ZIGZAG STITCH




To neaten seam edges and for securing and decorative purposes. Both the width and the length of this stitch can be altered.


3-STEP ZIGZAG STITCH




Made up of small, straight stitches. This stitch is decorative as well as functional, and is often found in lingerie. The stitch length and width can be altered.

BLIND HEM STITCH


Made in conjunction with the blind hem foot. A combination of straight stitches and a zigzag stitch (see opposite page). Used to secure hems.

OVEREDGE STITCH


Made in conjunction with the overedge foot. The stitch is used for neatening the edge of fabric. The width and length of the stitch can be altered.

STRETCH STITCH


Also known as a lightning stitch. This stitch is recommended for stretch knits, but is better used to help control difficult fabrics.

BASIC BUTTONHOLE STITCH

Square on both ends. Used on all styles of garment.

ROUND-END BUTTONHOLE STITCH

One square end and one round end. Used on jackets.

KEYHOLE BUTTONHOLE STITCH

One square end and one end shaped like a loop. Used on jackets.

DECORATIVE STITCHES

Sewing machines are capable of producing decorative linear stitches. These can be used to enhance the surface of work or a seam as they add interest to edges. Or, when worked as many rows together, they can be used to create a piece of embroidered fabric.

**3-THREAD SERGER STITCH**

Stitched using three threads on the serger. Used to neaten the edge of fabric to prevent fraying.

4-THREAD SERGER STITCH

Made using four threads on the serger. Used to neaten edges and to construct stretch knits.






MACHINE ARROWHEADS

This is a built-in stitch on many sewing machines. Used to secure weak points.

How to make a plain seam

LEVEL OF DIFFICULTY *

A plain seam is $\frac{5}{8}$ in (1.5 cm) wide. It is important that the seam is stitched accurately at this measurement, otherwise the item being made will come out the wrong size and shape. There are guides on the plate of the sewing machine that can be used to help align the fabric.




Making a seam with the serger

LEVEL OF DIFFICULTY **

Use this when constructing stretch knits.

1 Put the fabric together, right side to right side.

2 Stitch the seam with a 4-thread serger stitch.



Seam neatening

LEVEL OF DIFFICULTY *

It is important that the raw edges of the seam are neatened or finished—this will make the seam hard-wearing and prevent fraying. The method of neatening will depend on the style of item that is being made and the fabric you are using.

PINKED




ZIGZAGGED




OVEREDGE STITCHED

This is found on most sewing machines. Select the overedge stitch on your machine. Using the overedge machine foot and the pre-set stitch length and width, machine along the raw edge of the seam.




CLEAN FINISHED

This is a very hard-wearing finish and is ideal for cottons and fine fabrics. Using a straight stitch, turn under the raw edge of the seam allowance by $\frac{1}{8}$ in (3 mm) and straight stitch along the fold.



3-THREAD SERGED





If you have a serger, you can neaten seams with a 3-thread serger stitch. It is one of the most professional ways to finish seams and is suitable for all types of fabric and items.



Hong Kong finish

LEVEL OF DIFFICULTY **





This is a great finish to use on wools and linens, to neaten the seams on unlined jackets. It is made by wrapping the raw edge with bias-cut strips.



French seam

LEVEL OF DIFFICULTY **




A French seam is a seam that is stitched twice, first on the right side of the work and then on the wrong side, enclosing the first seam. The French seam has traditionally been used on delicate garments such as lingerie and on sheer and silk fabrics.



Run and fell seam

LEVEL OF DIFFICULTY **




Some garments require a strong seam that will withstand frequent washing and wear and tear. A run and fell seam, also known as a flat fell seam, is very strong. It is made on the right side of a garment and is used on the inside leg seam of jeans, and on men's tailored shirts.



Self-bound seam

LEVEL OF DIFFICULTY **



Another strong seam, this is constructed in a similar way to the run and fell seam (see opposite page), but on the wrong side of the work. It is used in children's wear.



Mock French seam

LEVEL OF DIFFICULTY **





When this seam is completed, it looks very similar to the French seam. A mock French seam is best used on cotton or firmer fine fabrics. It is constructed on the wrong side of the work.



Slotted seam

LEVEL OF DIFFICULTY **


A slotted seam is a decorative seam, shown on the right side. The edges of the seam open to reveal an under layer, which could be a contrasting fabric.



Top-stitched seam

LEVEL OF DIFFICULTY **


A top-stitched seam is very useful as it is both decorative and practical. This seam is often used on crafts and soft furnishings as well as garments.



Lapped seam

LEVEL OF DIFFICULTY **





Also called an overlaid seam, a lapped seam is constructed on the right side of the garment. It is a very flat seam when it is finished.



Corded seam

LEVEL OF DIFFICULTY **

A seam with piping in it can add interest to an otherwise plain garment. This is also a useful technique if you are joining two fabrics that are different. The piping is made first, prior to its being inserted in the seam.






Seams on difficult fabrics




LEVEL OF DIFFICULTY **

Some fabrics require specialist care for seam construction because they are very bulky, as you find with a fur fabric, or so soft and delicate that they appear too soft to sew. On a sheer fabric, the seam used is an alternative to a French seam; it is very narrow when finished and presses very flat. Making a seam on suede is done by means of a lapped seam. As some suede-effect fabric has a fake fur on the other side, the seam is reversible.


A SEAM ON SHEER FABRIC



A SEAM ON SUEDE OR SUEDE-EFFECT FABRIC



A SEAM ON FUR FABRIC




Stitching corners and curves

LEVEL OF DIFFICULTY **


Not all sewing is straight lines. The work will have curves and corners that require negotiation, to produce sharp clean angles and curves on the right side. The technique for stitching a corner shown below applies to corners of all angles. On a thick fabric, the technique is slightly different, with a stitch taken across the corner, and on a fabric that frays badly the corner is reinforced with a second row of stitches.

STITCHING A CORNER


1 Pin the fabric together, right side to right side.



2 Stitch a seam at $\frac{5}{8}$ in (1.5 cm).




3 On reaching the corner, insert the machine needle into the fabric.




4 Raise the presser foot and turn the fabric through 90 degrees (this is pivoting at the corner).

5 Lower the presser foot and continue stitching in the other direction.



6 The stitching lines are at right angles to each other, which means the finished corner will have a sharp point when turned through to the right side.




STITCHING A CORNER ON HEAVY FABRIC



1 On a thick fabric, it is very difficult to achieve a sharp point, so instead a single stitch is taken across the corner. First stitch to the corner.

2 Insert the needle into the fabric, then lift the presser foot. Turn the fabric 45 degrees. Put the foot down again and make one stitch.


3 With the needle in the fabric, lift the foot and turn the fabric 45 degrees again. Lower the foot and continue stitching along the other side.




STITCHING A REINFORCED CORNER




STITCHING AN INNER CORNER



STITCHING AN INNER CURVE



STITCHING AN OUTER CURVE




REDUCING SEAM BULK

It is important that the seams used for construction do not cause bulk on the right side. To make sure this does not happen, the seam allowances need to be reduced in size by a technique known as layering a seam. They may also require V shapes to be removed, which is known as notching, or the seam allowance may be clipped.

Layering a seam

On the majority of fabrics, if the seam is on the edge of the work, the fabric in the seam needs reducing. The seam allowance closest to the outside of the garment or item stays full width, while the seam allowance closest to the body or inside is reduced.





Cut along one side of the seam to reduce the fabric in the seam allowance by half to one third of its original width.

Reducing seam bulk on an inner curve

LEVEL OF DIFFICULTY *


For an inner curve to lie flat, the seam will need to be layered and notched, then understitched to hold it in place (see opposite page).




Reducing seam bulk on an outer curve

LEVEL OF DIFFICULTY *


1 Make the seam, stitching along the outer curve.



2 Layer the seam (see opposite page).




3 Clip through the seam allowances to reduce bulk.



4 Turn through to the right side and press.




5 Understitch the seam (see below) to finish.



Stitch finishes

LEVEL OF DIFFICULTY **

TOP-STITCHING



A top-stitch is a decorative, sharp finish to an edge. Use a longer stitch length, of 3.0 or 3.5, and machine on the right side of the work, using the edge of the machine foot as a guide.

UNDERSTITCHING



Understitching is used to secure a seam that is on the edge of a piece of fabric. It helps to stop the seam from rolling to the right side. First make the seam, then layer, turn, and press on to the right side. Open the seam again and push the seam allowance over the layered seam allowance. Machine the seam allowance down.

An outer curve also needs layering and notching or clipping to allow the fabric to turn to the right side, after which it is understitched.






DARTS, TUCKS, PLEATS, AND GATHERS

Shape is put into a piece of flat fabric by means of a dart, a tuck, a pleat, or a gather. It may be to shape the fabric around the body or shape for crafts and soft furnishings.

DARTS

A dart is used to give shape to a piece of fabric so that it can fit around the contours of the body. Some darts are stitched using straight stitching lines and other darts are stitched using a slightly curved line. Always stitch a dart from the point to the wide end because you are able to sink the machine needle into the point accurately and securely.

Directory of darts




BUST DART



CONTOUR OR DOUBLE-POINTED DART



FRENCH DART



WAIST DART










ELBOW DART

Plain dart

LEVEL OF DIFFICULTY *

This is the most common type of dart and is used to give shaping to the bust in the bodice. It is also found at the waist in skirts and pants to give shape from the waist to the hip.




Shaping darts to fit


LEVEL OF DIFFICULTY **

Our bodies often curve, and the straight line of the dart may not sit closely enough to our own personal shape. The dart can be stitched slightly concave or convex so it follows our contours. Do not move the curve out by more than $\frac{1}{8}$ in (3 mm).

CONVEX DART



CONCAVE CURVE



Contour or double-pointed dart

LEVEL OF DIFFICULTY **

This type of dart is like two darts joined together at the fat end. It is used to give shape at the waist of a garment. It will contour the fabric from the bust into the waist and then out again for the hip.

1 Tailor tack the dots on the pattern piece that mark the dart.

2 Cut through the loops in the tailor's tacks and remove the pattern.

Darts closer together at waist

3 Bring the tailor's tacks together, keeping the fabric right side to right side, and pin the tacks together.

4 Make a row of basting stitches just outside the pin line.

5 Machine stitch following the tailor-tack line, starting at one end and curving out to the widest point, then back to the other point, securing the machine stitching at both ends.

6 Remove the basting.






7 Clip across the fold in the fabric at the widest point, to allow the dart to be pressed to one side.

8 Press the dart to one side. Contour darts are normally pressed toward the center front or center back.

French dart

LEVEL OF DIFFICULTY ***

A French dart is used on the front of a garment only. It is a curved dart that extends from the side seam at the waist to the bust point. As this is a long dart that is shaped, it will need to be slashed prior to construction, in order for it to fit together and then lie flat when pressed.



Pressing a dart



If a dart is pressed incorrectly, this can spoil the look of a garment. For successful pressing, you will need a tailor's ham and a steam iron on a steam setting. A pressing cloth may be required for delicate fabrics such as silk, satin, and chiffon, and for lining fabrics.




TUCKS

A tuck is a decorative addition to any piece of fabric, and can be big and bold or very delicate. Tucks are made by stitching evenly spaced folds into the fabric on the right side, normally on the straight grain of the fabric. As the tucks take up additional fabric, it is advisable to make them prior to cutting out.



Directory of tucks




BLIND TUCKS




CROSS TUCKS




PLAIN TUCKS



SHELL TUCKS



SPACED TUCKS







PLAIN DARTED TUCKS

Plain tucks

LEVEL OF DIFFICULTY **

A plain tuck is made by marking and creasing the fabric at regular intervals. A row of machine stitches are then worked adjacent to the fold.



Other simple tucks

LEVEL OF DIFFICULTY **

These tucks are also made by marking and creasing the fabric. The positioning of the machine stitching determines the type of tuck.

SPACED TUCKS

These are similar to a plain tuck, but with wider regular spacing. Press the tucks in place along the foldlines and pin. Machine $\frac{3}{8}$ in (1 cm) from the foldline. Press all the tucks in one direction.



PIN TUCKS

These narrow, regularly spaced tucks are stitched very close to the foldline, which may require moving the machine needle closer to the fold. Use the pintuck foot on the sewing machine.



TWIN NEEDLE TUCKS

For these regularly spaced tucks, use the twin needle on the sewing machine. The twin needle produces a shallow tuck that looks very effective when multiple rows are stitched.



BLIND TUCKS

Blind tucks are stitched so that they touch, and no machining lines show. Fold back all but one tuck and stitch it in place. Continue stitching the tucks in this way so that the folded edge of each covers the machine line of the previous tuck.



Shell tucks


LEVEL OF DIFFICULTY **

A shell tuck is very decorative as it has a scalloped edge. Shell tucks can be easily stitched using the sewing machine. On heavy fabric and delicate fabrics, it may be preferable to make the tucks by hand.

MACHINE SHELL TUCKS


1 Mark the foldlines on the fabric, then fold and press.

2 Baste the folds in place.




3 Use the embroidery foot on the sewing machine and set the sewing machine to a shell hem stitch.

4 Stitch along the fold, keeping the fold close to the inside opening of the machine foot.




5 The finished tucks should be stitched at regular intervals.




SHELL TUCKS BY HAND

1 Baste the foldlines for the tucks in place.

2 Using a double thread in the needle, make two or three running stitches.




3 Every ½ in (1.25 cm), make an over-stitch through the fold to produce a scallop.




Corded or piped tucks

LEVEL OF DIFFICULTY **

These are very substantial tucks that stand proud of the fabric. This type of tuck is best used in soft furnishings.



- 1 Mark the folds on the fabric and press. Place piping cord into the folds.
- 2 Baste to hold the cord in place.



- 3 Using the zip foot on the sewing machine, stitch close to the cord.




- 4 The finished corded tucks are spaced neatly at regular intervals.

Darted tucks


LEVEL OF DIFFICULTY **

A tuck that stops to release the fullness is known as a darted tuck. It can be used to give fullness at the bust or hip. The shaped darted tuck is stitched at an angle to release less fabric, while the plain darted tuck is stitched straight on the grainline.

SHAPED DARTED TUCKS



- 1 Transfer any pattern markings to the fabric.
- 2 Fold the fabric right side to right side. On the wrong side of the fabric, stitch at an angle to the folded edge.



- 3 Stop at the point indicated on your pattern.
- 4 Secure the machining.

PLAIN DARTED TUCKS



- 1 Make in the same way as a shaped darted tuck (see left), but stitch parallel to the folded edge.
- 2 Stop as indicated on the pattern.



- 3 The tuck as seen from the right side.


Cross tucks

LEVEL OF DIFFICULTY **

These are tucks that cross over each other by being stitched in opposite directions.



- 1 Press the crease lines into the fabric, both vertically and horizontally.
- 2 Stitch all the vertical tucks first: fold the fabric wrong side to wrong side along the crease lines. Stitch $\frac{3}{16}$ in (5 mm) from the folded edge.




- 3 Stitch all the horizontal tucks in the same way.
- 4 Press all the vertical or horizontal tucks in the same direction.


PLEATS

A pleat is a fold or series of folds in fabric. Pleats are most commonly found in skirts where the pleats are made to fit around the waist and hip and then left to fall in crisply pressed folds, giving fullness at the hemline. It is important that pleats are made accurately, otherwise they will not fit the body and will look uneven. Foldlines and placement lines, or foldlines and crease lines, are marked on the fabric from the pattern. It is by using a combination of these lines and the spaces between them that the pleats are made.


Directory of pleats




BOX PLEATS



GODET IN A SEAM




GODET IN A SPLIT



INVERTED PLEATS



KICK PLEAT



KNIFE PLEATS

Pleats on the right side


LEVEL OF DIFFICULTY **

Knife pleats are normally formed on the right side of fabric. They can all face the same direction or may face opposite directions from opposite sides of the garment. Knife pleats have foldlines and placement lines.

1 Mark the placement lines and foldlines with trace tacks. Use one color thread, such as red, for placement lines.

2 Use a contrasting color thread, such as blue, to mark foldlines.

3 Cut through the thread loops and remove the pattern pieces carefully.



4 Fold the fabric along the foldline, creasing accurately along the trace tacks.

5 Bring the creased line on to the placement line. Pin to secure.



6 Baste along the foldlines about $\frac{1}{16}$ in (2 mm) from the folded edge, through all the layers.



7 Remove the pins and the trace basting on this part of the pleat.

8 With the right side of the fabric uppermost, cover with a silk organza pressing cloth.



9 Using a steam iron on a steam setting, press the pleats in place. Keep the iron still as opposed to moving it around, and eject a shot of steam each time you lift it to a new position. Repeat this action across all of the pleats.

10 Turn the fabric to the wrong side and insert thin strips of construction paper under the pleat fabric.



11 Press again with the steam iron and a silk organza cloth. The paper will prevent the fabric from leaving an imprint on the right side.


Pleats on the wrong side

LEVEL OF DIFFICULTY **

Some pleats, including box (shown below) and inverted pleats, are formed on the wrong side of the fabric. As the pleats are made on the wrong side, you can mark the crease lines and foldlines with a tracing wheel and dressmaker's carbon paper. Use a ruler to guide the tracing wheel, because these pleats need to be straight lines.


1 Mark the crease lines and foldlines on the wrong side of the fabric, using different colors for the different lines. The lines must be marked down the full length of the fabric.

2 Also mark the stop line that shows where to stop stitching. Remove the pattern pieces.




3 Bring the two crease lines that are either side of the foldline together and pin in place.

4 Be sure the foldline is along the fold in the fabric.




5 Baste through the two layers of fabric where the crease lines have been pinned together, along the entire length of the pleat.



6 Machine along the crease lines.


7 Stop at the stop marking. Secure the machine stitching.

8 Flatten the pleat on the wrong side so that the foldline is lying on top of the machine stitching. Make sure that the fabric on either side of this foldline to the crease line is equal on both sides.



9 Cover the pleats on the wrong side with a silk organza pressing cloth and press, using a steam iron with a shot of steam.

10 Press each section of the pleat in turn, lifting the iron rather than moving it on the fabric.



11 If the fabric is in danger of being marked on the right side with the pleats, place some strips of construction paper under the pleats on the wrong side, then press again on the wrong side.




Pleats with a separate underlay

LEVEL OF DIFFICULTY ***

Sometimes a box pleat is constructed with a separate piece of fabric or underlay. This technique is usually done on large, single box pleats or on a pleat made using thicker fabric, because it reduces the bulk. The seam to make this pleat is much wider than normal, as it is the width of the pleat.

1 Mark the stitching line with trace bastes. Cut through the thread loops and carefully pull away the pattern piece.

2 Place the two pieces of fabric together, right side to right side. Match the notches and trace basting.



3 Baste along the trace bastes that mark the stitching line, removing the trace basting as you do so.

4 Machine the seam to the stop point.

5 Press the seam open along its full length.



6 Take the underlay and place carefully on to the pressed seam, matching the notches. The wrong side of the underlay should be uppermost.

7 Pin the underlay in place, being careful to pin it just to the edge of the seam and not through to the main fabric.




8 On this type of pleat, the hem has to be constructed before all the pleats can be made. Stitch either side of the underlay to the edge of the pleat, stopping at least 4 in (10 cm) above the raw hem edge.

9 Remove the basting stitches that are holding the pleat together.

10 Turn up the hem including the pleat. Separately turn up the underlay to match.

11 Pin the underlay and the pleat back together from where the machine stitching stopped, down through the hem. Make sure that on the right side the hem is even through this area.



12 Neaten the seams using your preferred method.

13 Remove the lower edge of the underlay/pleat seam, then blanket stitch or whip stitch. Finish by pressing.

Top-stitching and edge-stitching pleats

LEVEL OF DIFFICULTY **


If a pleat is top-stitched or edge-stitched, it will hang correctly and always look crisp. It will also help the pleats on the skirt to stay in shape when you are sitting. Try to stitch both the top-stitching and the edge-stitching the entire length of the skirt, from the hem to the waist.

TOP-STITCHING KNIFE PLEATS

1 Once the knife pleats have been pressed and all bastes and markings removed, place some pins across the pleat to stop it from moving.

2 Machine stitch from the right side approx $\frac{1}{16}$ in (2 mm) from the fold.

3 Start the stitching at the lower end of the pleat and stitch to the waist.




TOP-STITCHING BOX PLEATS THAT HAVE A SQUARE END

1 This requires stitching down on either side of the foldline. Stitch down one side about $\frac{1}{16}$ in (5 mm) from the foldline.

2 Pivot and stitch horizontally across the end of the stitching of the pleat.


3 Pivot again and stitch up the other side of the foldline about $\frac{1}{16}$ in (5 mm) from the foldline.



TOP-STITCHING BOX PLEATS THAT HAVE A POINTED END

1 Stitch down one side $\frac{1}{16}$ in (5 mm) from the foldline, then pivot and stitch diagonally to the center.

2 Pivot again and stitch diagonally the other side and back to the waist $\frac{1}{16}$ in (5 mm) from the foldline.



EDGE-STITCHING KNIFE PLEATS

1 After pressing the pleats into shape, stitch $\frac{1}{16}$ in (2 mm) from the fold.

2 Stitch along the entire length of the fold.




EDGE-STITCHING AND TOP-STITCHING PLEATS

1 Edge-stitch first the edge of the pleat about $\frac{1}{16}$ in (2 mm) from the folded edge.

2 Stop the edge-stitching just above the point where the pleat is to be top-stitched.

3 Place the machine needle into the pleat, through all layers, four or five stitches below where the edge-stitching stops.

4 Top-stitch through all the layers, continuing at $\frac{1}{16}$ in (2 mm) from the fold, to the waist.




TOP-STITCHING KICK PLEATS OR INVERTED PLEATS

1 This pleat is pressed to the right. Just below the stitching line that makes the pleat, stitch a line diagonally, to secure the pleat fabric at the back.

2 Make sure the stitching line finishes exactly on the foldline.

3 Pull the ends of the machine stitching through to the reverse.





Staying pleats


LEVEL OF DIFFICULTY ***

Staying a pleat is a technique used to reduce the bulk of the pleat, especially in the hip area. There are various ways of doing this and the method chosen will depend on the type of pleat, the fabric used, and your personal preference.

SELF-STAYING BOX PLEATS OR INVERTED PLEATS



STAYING KNIFE PLEATS ON THICKER FABRIC



Hemming pleats


LEVEL OF DIFFICULTY ***

Most pleated garments or soft furnishings are hemmed after the pleats have been constructed; however, in some cases pleats can be hemmed first. This technique is only used for garments with all-around pleats or that have to follow a checker or stripe.

HEMMING KNIFE PLEATS OR INVERTED PLEATS

1 Make sure the pleat has been well pressed. Press the hem up into place, then open the pleat out to reveal the crease lines.

2 Reduce the bulk in the seam in the area of the hem, from the raw edge to the top edge of the hem when folded into place.



3 Clip through the seam allowance.

4 Press this part of the seam allowance in the opposite direction to the seam.

5 Turn up the hem.

6 Press the pleat back into position.




7 Machine through the crease line in the hem.

HEMMING BOX PLEATS BEFORE THE GARMENT IS FINISHED

1 Turn up the hem.

2 Make the seam and press open.



3 Remove the lower edges of the seam by trimming diagonally.

4 Blanket stitch or whip stitch across these corners.

HEMMING BOX PLEATS AFTER THE GARMENT IS FINISHED

1 Press the pleat into position and press the hem into position.




2 Reduce the seam allowance below the crease line of the hem.



3 Turn up the hem.

4 Match the stitching lines and press the pleat for the final time.

SECURING PLEATS AT THE HEM



The bottom of every pleat on a garment can be secured temporarily with two or three cross stitches.

Adjusting pleats to fit

LEVEL OF DIFFICULTY ***


If a pleated skirt is either too big or too tight at the waist or hip, a small adjustment on each pleat can make a huge difference. Simply take the amount to be added or removed and divide it by the number of pleats. If the adjustment is not the same on all the pleats, they will look unbalanced.

LETTING OUT PLEATS FORMED ON THE RIGHT SIDE

1 Mark the crease lines and foldlines.

2 Take the foldline and place it slightly to the left of the placement line.

3 Taper back on to the placement line at the end of the adjustment. Machine into place.




TAKING IN PLEATS FORMED ON THE RIGHT SIDE

1 Mark the crease lines and foldlines.

2 Take the foldline and, instead of placing it on top of the placement line, overlap it by the small amount required.


3 Taper back on to the placement line at the end of the adjustment, then machine in place.



LETTING OUT PLEATS FORMED ON THE WRONG SIDE

1 The red stitching indicates the original stitching line for the pleat. Let the pleat out, stitching closer to the foldline.


2 The blue stitching line indicates the adjustment.



TAKING IN PLEATS FORMED ON THE WRONG SIDE

1 The red stitching line indicates the original stitching line for the pleat. Take the pleat in, stitching further from the foldline.



2 The blue stitching line indicates this adjustment.



Godet in a seam

LEVEL OF DIFFICULTY ***

A godet is a type of pleat that is inserted into a garment to give fullness at the hem edge. It is a segment of a circle, usually triangular in shape, but also sometimes a half circle—the size of the godet depends on the fullness required. The godet may go from hem to knee or even hem to thigh, according to the style of the skirt. The easiest way to insert a godet is in a seam.




Godet in a split

LEVEL OF DIFFICULTY ****


Sometimes there are not enough seams in a garment for the number of godets that you would like to insert. If that is the case, a split must be made in the fabric at the hemline to accommodate each godet. A piece of silk organza is sewn on to the point of the split to strengthen it.

1 Mark the split on the skirt. Place a small square of silk organza at the top of the marked split, on the right side of the fabric.



2 Stay stitch on both sides of the marked split.

3 Slash the split open from the hem to the given point.



4 Pull the organza square to the wrong side.

5 Cut out the godet and mark the stitching stop point.

6 Pin the godet along one side of the split, right side to right side. Allow a $\frac{3}{8}$ in (1.5 cm) seam allowance on the godet and the minimum seam allowance on the split.



7 Machine the pinned godet in place. Stop at the tailor's tack in the godet.

8 Machine the other side of the godet to the split. Make sure the stitching lines meet exactly at the point of the split.



9 On the right side, there should be no creases at the top of the godet. Press gently to finish, using just the toe of the iron.







Pleats on curtains


LEVEL OF DIFFICULTY **

Pleats are used in soft furnishings, particularly at the top of curtains, to reduce the fabric so that the curtain will fit on to its track and fit the window. The easiest way to pleat the upper edge of a curtain is to apply a curtain tape. Tapes are available in various depths and will pull the curtain into pencil pleats or goblet pleats. The most common tape used for pencil pleating is $3\frac{1}{4}$ in (8 cm) deep. A curtain is normally cut two and a half to three times the width of the window. The curtain tape will reduce the fabric by this much as it pleats up.

PREPARING THE CURTAIN TO TAKE THE TAPE



MAKING A POCKET FOR THE STRINGS



PENCIL PLEATS

1 Take the curtain tape and release the strings at the one end, making sure they are all visible on the same side.

2 Place the top of the tape $\frac{3}{16}$ in (5 mm) down from the folded edge of the curtain. Pin in place, stretching the tape as you do so. Turn under the short end, avoiding the strings and pin.

3 Machine the upper edge of the tape to the curtain fabric. Make sure the strings stay free.

4 Before stitching the lower edge of the tape, place the pocket you made under the end of the tape.

5 Pin the tape and the pocket in place. Machine stitch the tape and pocket.

6 Pull up the strings in the tape from the end with the pocket to make the pleats.

7 Tie the strings together and place in the pocket.

8 At the opposite end of the tape, stitch across each string individually to prevent it from being pulled out.

9 Turn the curtain over to check that the pencil pleats are evenly spaced and will fit the window. Adjust if necessary.

GOBLET PLEATS

1 Goblet pleats are three pleats together at regular intervals. When the tape is pulled up, the pleats are close together at the base and fan out at the top. Prepare the curtain to take the tape and make the pocket (see opposite page).

2 Attach the tape in the same way as for pencil pleats (above).

3 After pulling up the tape, secure it by hand on the right side at the base of the tape.

4 Hand stitch the upper edge of the pleats at the back.


GATHERS

Gathers are an easy way to draw up a piece of larger fabric so that it will fit on to a smaller piece of fabric. They often appear at waistlines or yoke lines. The gather stitch is inserted after the major seams have been constructed, and it is best worked on the sewing machine using the longest stitch length that is available. On the majority of fabrics two rows of gather stitches are required, but for very heavy fabrics it is advisable to make three rows. Try to stitch the rows so that the stitches line up under one another.


Directory of gathers




GATHERS



SMOCKING



WAFFLE SHIRRING







CORDED SHIRRING

How to make and fit gathers

LEVEL OF DIFFICULTY *



Once all the main seams have been sewn, stitch the two rows of gathers so that the stitches are inside the seam allowance. This should avoid the need to remove them, because removing gathers after they have been pulled up can damage the fabric.



Corded gathers

LEVEL OF DIFFICULTY **



Corded gathers are gathers that are pulled up over a narrow piping cord or thick thread. This technique is used for furnishing fabrics, where machine gathers may not be strong enough.



Gathers on the serger

LEVEL OF DIFFICULTY ***


An attachment can be purchased for the serger that will enable you to gather fine fabrics such as net, chiffons, and georgettes, on to other fabrics. This is a really useful technique if large quantities of a fine fabric are to be gathered, such as bridal petticoats and frills in soft furnishings.



Staying a gathered seam

LEVEL OF DIFFICULTY **



A gathered seam is often stayed by stitching on cotton stay tape, to ensure the gathers remain in place and also to help strengthen the seam.



Joining two gathered edges together

LEVEL OF DIFFICULTY ***

On some garments it may be necessary to join together two gathered edges. This usually happens when gathering a skirt on to a gathered bodice. The one side, usually the skirt, is gathered first on to a stay tape and the second side is gathered to fit, then stitched in place.





Shirring


LEVEL OF DIFFICULTY **

Shirring is the name given to multiple rows of gathers. It is an excellent way to give fullness in a garment. If made using shirring elastic in the bobbin, shirring gathers can stretch. On heavier fabrics, such as for soft furnishings, static shirring is more suitable.


MACHINE SHIRRING




WAFFLE SHIRRING



CORDED SHIRRING



3 Knot the cord at one end to prevent it from pulling through.








6 Knot the other end of the cord to secure.

Smocking

LEVEL OF DIFFICULTY **

Smocking is one of the oldest ways of gathering fabric. It is very decorative and can add interest to a garment. Smocking involves pulling up multiple rows of gathers that have been stitched in by hand, in line with each other, to produce fine tubes in the fabric. These tubes are then stitched over. Smocking dots that can be heat-transferred to the fabric are used as a guide for the hand gathers. Dots can be purchased with different spaces between them.



Smocking for cushions

LEVEL OF DIFFICULTY **

1 Mark the dots on the wrong side of the fabric with chalk. Use two different colors to distinguish the different kinds of dots.



Smocking can be used in a much larger format to produce a decorative effect on cushions. Patterns and templates can be purchased for this effect.

2 Stitch adjacent red dots to red dots and blue to blue using an over-sewing stitch.



3 Continue working across the fabric, joining the blue dots to blue dots and red dots to red dots.




4 On the right side of the fabric, a chevron smocking effect will be produced.




RUFFLES

Ruffles can be single layer or double layer and are used to give a decorative gathered effect to a garment. The amount of fullness in a ruffle depends on the fabric used—to achieve a similar result, a fine, thin fabric will need twice the fullness of a thicker fabric.


Directory of ruffles




PLAIN RUFFLE



RUFFLE WITH A HEADING



CIRCULAR RUFFLE



DOUBLE RUFFLE

Plain ruffle

LEVEL OF DIFFICULTY **

A plain ruffle is normally made from a single layer of fabric cut on the straight of the grain. The length of the fabric needs to be at least two and a half times the length of the seam into which it is to be inserted or of the edge to which it is to be attached. The width of the ruffle depends on where it is to be used.

1 Turn under one long edge $\frac{3}{16}$ in (5 mm), then turn under again by the same amount.

2 Pin in place, then machine with a straight stitch.

3 Press the machined edge flat.

4 Place two rows of gather stitches along the raw edge—one row at $\frac{3}{8}$ in (1 cm) and the second row at $\frac{1}{2}$ in (1.2 cm). Pull the threads to gather the fabric. The ruffle is now ready to be attached.

Wrong side of ruffle

Finished hem edge

Ruffle with a heading

LEVEL OF DIFFICULTY **

This type of ruffle can give a decorative effect on clothing and soft furnishings.

1 Neaten one long edge as for a plain ruffle (steps 1–3, above).

2 Turn down the other long edge—the amount of the turn down is the depth of the required heading plus a seam allowance of $\frac{3}{8}$ in (1.5 cm).

3 Baste the heading in place.

4 Insert the two rows of gather stitches.

5 Pull up the stitches to make the gathers.


6 After gathering, there will be gathers with a ruffle on one side of the stitch line and a short gathered heading on the other. Pull out the basting stitches.

Double ruffle version 1

LEVEL OF DIFFICULTY **

This is a great ruffle on fine fabrics as it can be highly decorative. Attach the ruffle to the garment by stitching through the center of the gather lines.

1 Neaten both long edges by turning the fabric once and then again, and machining (see Plain ruffle, steps 1–3, page 135).



Wrong side of fabric

2 Work two rows of gather stitches lengthwise down the center of the fabric.

3 Pull up the gather stitches to create a ruffle to fit.



4 Turn the ruffle over to the right side to check that the gathers are equally spaced. Adjust if necessary, then attach to the garment.

Double ruffle version 2

LEVEL OF DIFFICULTY **

This ruffle has one side longer than the other and is fashioned from two plain ruffles.

1 Cut two pieces of fabric for the ruffle, one wider than the other. Neaten one long edge of each piece (see Plain ruffle, steps 1–3, page 135).

2 Pin the pieces of fabric together along the raw edges, right sides up, making sure the shorter piece is on the top.

3 Insert two rows of gather stitches through the two layers.

4 Pull the threads to gather the double ruffle to fit.



Double ruffle version 3

LEVEL OF DIFFICULTY **

This is a useful ruffle on a fabric that is prone to fraying.


1 Cut the fabric for the ruffle twice the required depth.

2 Fold the fabric lengthwise, wrong side to wrong side.

3 Pin the raw edges together.

4 Insert gathers along the raw edge.


5 Pull up the gathers to fit.



Stitching into a seam

LEVEL OF DIFFICULTY **

Once the ruffle has been constructed it can either be inserted into a seam or attached to the edge of the fabric (see page 138). The two techniques below apply to both single and double ruffles.



Stitching around a corner

LEVEL OF DIFFICULTY ***

It can be difficult to stitch a ruffle to a corner and achieve a sharp point. It is easier to fit the gathers into a tight curve, which can be done as the ruffle is being applied to the corner.



Stitching a ruffle to an edge

LEVEL OF DIFFICULTY ***

SELF-BOUND FINISH

If a ruffle is not in a seam then it will be attached to an edge. The edge of the seam will require neatening, which is often best done by using a binding method as it is more discreet. A self-bound edge, where the seam is wrapped on to itself, is suitable for fine, delicate fabrics. For thicker fabrics, use a bias binding to finish the edge.

1 Place the gathered ruffle to the edge of the fabric, right side to right side. Pin in place.

2 Machine the ruffle to the fabric using a $\frac{5}{8}$ in (1.5 cm) seam allowance.

3 Trim the gathered side of the seam allowance down to half.

4 Wrap the longer, fabric side of the seam over the gathered seam, tucking under the raw edge. Pin in place.

5 Machine the wrapped seam to secure. Make sure it is attached to the seam only.

BIAS-BOUND FINISH

1 Machine the gathered ruffle to the edge of the fabric, right side to right side, using a $\frac{3}{8}$ in (1.5 cm) seam allowance (see steps 1 and 2, opposite).

2 Use $\frac{3}{8}$ in (2 cm) wide bias binding. Stitch the crease in the bias over the machine stitching.

3 Trim back both sides of the seam allowance.



4 Wrap the bias over to the wrong side of the seam. Pin in place.




5 Machine stitch the other side of the bias close to the fold.



Attaching a double frill to an edge

LEVEL OF DIFFICULTY ***


This is a very neat way to attach a double ruffle to an edge as the seam is hidden. The ruffle is stitched first to the wrong side of the work and then folded on to the right side.



1 Place the ruffle on to the fabric with the gathers at $\frac{3}{8}$ in (1.5 cm) from the raw edge. Pin in place.



2 Machine in place, close to the top stitching line of the gathers.



3 Turn the frill to the right side of the fabric. Trim away half the seam allowance behind the frill.

4 Machine stitch along the second row of gathering stitches.

Circular ruffle





LEVEL OF DIFFICULTY ***

A ruffle can be cut using a circular shape. The advantage is that there are no gathers because the center part of the circle is cut out to make a seam. The fullness occurs as the inner edge of the circle is stretched and attached. For a circular ruffle you will need a pattern.

MAKING THE PATTERN FOR A CIRCULAR RUFFLE

You need pattern paper to cut your circle and a compass created from a pencil with a piece of string tied on to it.

- 1 Draw an inner circle, the circumference of which will be the length of the seam into which the ruffle is to be attached. You can join several ruffles together to achieve this measurement.
- 2 Draw in the standard seam allowance.
- 3 From the seamline measure out the depth of the ruffle, then draw to make another circle.
- 4 Cut out the larger circle, then cut out the inner circle. Cut through the pattern, from the outer edge to the inner edge.



8 Place the ruffle to the edge where it is to be attached, right side to right side. Pin in place.



9 Machine in place just below the stay stitching.



NEATENING THE RUFFLE EDGE WITH A ROLLED HEM

An alternative way to neaten the outer edge is to use the sewing machine with the rolled hem foot and a straight stitch.



Another alternative is a rolled hem on the sewing machine using the rolled hem foot and a zigzag stitch.




Double circular ruffle

LEVEL OF DIFFICULTY ***

On very lightweight fabrics such as chiffon or silk, it is advisable to make a double-layer ruffle as it will hang better. With this method there is no edge to neaten.


1 Cut two circular ruffles (see opposite) and join them together, right side to right side. Pin to secure.

2 Machine the outer edges together with a $\frac{1}{2}$ in (1.5 cm) seam allowance. Continue the stitching along the short ends.




4 Cut out V shapes to reduce the bulk.


3 Trim down one half of the seam allowance.



5 Turn through to the right side, pushing out the corners. Press.

6 Stay stitch the inner edge through both layers. The ruffle is now ready to be attached (see steps 8 and 9, above left).








FACINGS AND NECKLINES

Edges on garments are often neatenened by means of a facing. This is a shaped piece of fabric, which may be stiffened with interfacing, attached to a neckline—or to an armhole or at a waist edge—for a strong finish.


FACINGS AND NECKLINES

The simplest way to finish the neck or armhole of a garment is to apply a facing. The neckline can be any shape to have a facing applied, from a curve to a square to a V, and many more. Some facings and necklines can add interest to the center back or center front of a garment.


Directory of necklines




ROUND NECK




SCOOP NECK




SQUARE NECK



SWEETHEART NECK



U-NECK




V-NECK


Applying interfacing to a facing

LEVEL OF DIFFICULTY *

INTERFACING FOR HEAVY FABRIC





INTERFACING FOR LIGHT FABRIC



Construction of a facing

LEVEL OF DIFFICULTY *

The facing may be in two or three pieces in order to fit around a neck or armhole edge. The facing sections need to be joined together prior to being attached. The photographs here show an interfaced neck facing in three pieces.



Neatening the edge of a facing

LEVEL OF DIFFICULTY **


The outer edge of a facing will require neatening to prevent it from fraying, and there are several ways to do this. Binding the lower edge of a facing with a bias strip makes the garment a little more luxurious and can add a designer touch inside the garment. Alternatively, the edge can be stitched or pinked (see opposite page).

1 Making your own bias strip is easy (see opposite page). Open out one folded edge of the bias strip and place to the outer edge of the facing, right side to right side.

2 Machine along the crease line in the bias.



3 Wrap the bias around to the wrong side of the work. Baste to hold in place.



4 Working from the right side of the facing, stitch in the ditch made by the bias-to-facing stitching.



5 On the right side of the facing, the bias-bound edge has a neat, professional finish.



HOW TO CUT BIAS STRIPS

1 Fold the fabric on to itself at 45 degrees so the selvedge edges are at right angles to each other. Pin in place.

2 Using tailor's chalk and a ruler, mark lines $1\frac{1}{2}$ in (4 cm) apart.

3 Cut along these lines to make bias strips.

4 Join the strips by placing them together right side to right side at 90 degrees to each other.

5 Machine across the join. There should be a triangle of fabric at either end of the seam.

6 Press the seam open.

7 Press under the edges of the bias strip with the iron by running the bias strip through a $1\frac{1}{2}$ in (25 mm) tape maker.

Other neatening methods

LEVEL OF DIFFICULTY *

The following techniques are alternative popular ways to neaten the edge of a facing. The one you choose depends upon the garment being made and the fabric used.

SERGED



The outer edge neatened with a 3-thread serger stitch.

PINKED



Machine stitched $\frac{3}{8}$ in (1 cm) from the edge and the raw edge trimmed with pinking shears.

ZIGZAG









The outer edge neatened with a zigzag stitch.

Attaching a neck facing

LEVEL OF DIFFICULTY **



This technique applies to all shapes of neckline, from round to square to sweetheart.



Facing a slashed neckline

LEVEL OF DIFFICULTY ***

A slashed neckline occurs at either the center front or the center back neck edge. It enables a close-fitting neckline to open sufficiently to go over the head.



Armhole facing

LEVEL OF DIFFICULTY **

On sleeveless garments, a facing is an excellent way of neatening an armhole because it is not bulky. Also, as the facing is made in the same fabric as the garment, it does not show.

- 1** Construct the armhole facing (see page 145) and neaten outer edge by preferred method.



- 2** Place the facing to the armhole, right side to right side. Match at the shoulder seams and at the underarm seam.

- 3** Match the notches, one at the front and two at the back. Pin the facing in place.



- 4** Machine around the armhole to attach the facing, taking a $\frac{3}{8}$ in (1.5 cm) seam allowance.

- 5** Trim the facing side of the seam allowance down to half.

- 6** Clip out some V shapes in the seam allowance to reduce bulk.



- 7** Turn the facing into position on the wrong side. Understitch by pressing the seam allowance on to the facing and machining down.



Understitching



- 8** On the underarm and shoulder seams, secure the facing to the seam allowance with cross stitches.




- 9** Press the stitched edge. On the right side, the armhole will have a neat finish.



Combination neck and armhole facing

LEVEL OF DIFFICULTY ***



This type of facing neatens the neck and the armhole edge at the same time. It needs to be stitched in place before the center back seam or the side seams are constructed.



Grown-on facing

LEVEL OF DIFFICULTY **

A facing is not always a separate unit. Many garments, especially blouses, feature what is known as a grown-on facing, which is where the facing is an extension of the front of the garment, cut out at the same time.



Bound neck edge



LEVEL OF DIFFICULTY **

Binding is an excellent way to finish a raw neck edge. It has the added advantage of being a method that can be used if you are short of fabric or you would like a contrast or decorative finish. You can use bought bias binding or a bias strip cut from the same or a contrasting fabric (see page 147). A double bias strip is used on fine fabrics.



BIAS-BOUND NECK EDGE VERSION 1



BIAS-BOUND NECK EDGE VERSION 2



DOUBLE BIAS-BOUND NECK EDGE



Piped neck edge

LEVEL OF DIFFICULTY **


This technique features a piping around the neck as well as a facing. A piped neckline looks very good on special-occasion wear.

1 Cut a strip of bias $1\frac{1}{2}$ in (4 cm) wide and as long as the required neck measurement plus $1\frac{1}{4}$ in (3 cm). Press in half lengthwise, wrong side to wrong side.




2 Turn under $\frac{5}{8}$ in (1.5 cm) at each end of the bias and secure a length of piping cord in the center using a machine stitch across it.

3 Fold the bias strip in half.




4 Machine close to the piping cord using a zipper foot.

5 Place the bias around the neck, right side to right side. Position the neatened end at the center back. Pin in place.




6 Machine around the neck using the zipper foot.

7 Attach the neck facing over the piped bias and machine in place.



8 Trim the seam allowance on the facing side of the seam.

9 Clip the seam allowance on the bias and neck of the garment.



10 Turn the facing to the wrong side.

11 Turn under the edge of the facing to the edge of the zipper.





12 Finished neckline with piped edge.



Plackets

LEVEL OF DIFFICULTY ***

A placket is an opening that stops partway down a bodice. It is made by applying two separate bands of fabric to the bodice. Care must be taken to ensure that the pattern pieces are accurately marked. A placket opening is popular on sportswear.






Necklines in stretch knits



LEVEL OF DIFFICULTY ***

When working with a stretch knit fabric, the neckline can be finished with a single banding or a more decorative double banding. The banding is usually attached with a 4-thread serger stitch, which enables the neck to stretch over the head. If you do not have a serger, you can use a 3-step zigzag stitch on the sewing machine.


SINGLE BANDING WITH SERGER



DOUBLE BANDING WITH SERGER





ATTACHING BANDING WITH A SEWING MACHINE



2 Neaten the raw edge with a 3-step zigzag stitch.

BANDING FOR A V NECK








COLLARS

Collars frame the face and neck, and are always a focal point on any garment. There are three main types: flat, stand, and rolled. To construct a symmetrical collar, careful and accurate marking and stitching are essential.


COLLARS

All collars consist of a minimum of two pieces, the upper collar (which will be on the outside) and the under collar. Interfacing, which is required to give the collar shape and structure, is often applied to the upper collar to give a smoother appearance to the fabric.


Directory of collars




FLAT COLLAR




PETER PAN COLLAR




BLOUSE COLLAR



SHAWL COLLAR



SHIRT COLLAR



STAND COLLAR

Flat collar


LEVEL OF DIFFICULTY **

A flat collar is the easiest of all the collars to construct, and the techniques used are the same for most other shapes of flat collar and facings.

1 Cut out the fabric for the collar accurately. Make sure the two halves match.


2 Cut out a fusible interfacing, being sure to cut on the same grain as the collar. Apply the interfacing to the upper collar.

3 Insert tailor's tacks at the center front point of the collar where indicated by a dot on the pattern piece.



4 Pin the upper collar and under collar together, right side to right side. Match any notches and make sure the cut edges match.

5 Machine stitch $\frac{5}{8}$ in (1.5 cm) along the raw outer curved edge to the lower edge of the collar. Make sure the machining at the center front goes through the tailor's tack. If you have problems stitching a curve, mark the fabric first with chalk.



6 Trim the under collar seam allowance to half of its width, which will reduce the bulk.

7 Trim around the curve with pinking shears, reducing both layers. This will allow the fabric to turn.



8 Clip the curve on the collar using small cuts at 90 degrees to the stitching line, clipping through the pinked seam.

9 Press the seam allowance of the upper collar on to the collar.

10 While the collar is still warm from the steam iron, turn to the right side.




11 Working from the inside of the collar, push all the seam allowance toward the under collar and machine it to the under collar. This is called understitching and will hold the collar in shape.

12 Understitch as far through the curve as you can.



13 Press the curved edge flat, making sure the seam is pushed out completely on the right side.



Attaching a flat collar

LEVEL OF DIFFICULTY ***

A flat collar can be attached to the neckline by means of a facing. Depending upon the style of the garment, the facing may go all around the neck, which is usually found on garments with center back openings, or just be at the front. The collar with no back facing has to be attached to the garment in stages.

FLAT ROUND COLLAR WITH NO BACK FACING

1 Construct the collar (see page 161).

2 Mark the center front points on the garment and the collar with tailor's tacks.

3 Place the collar to the neckline, right side to right side. Match the notches.

Grown-on front facing, interfaced to foldline

4 Pin in place, pinning just to the tailor's tacks.

5 Snip the collar at the tailor's tacks. The collar should be loose across the back neck.

6 Machine the under collar across the back of the neck first, stitching from tailor's tack to tailor's tack. Keep the upper collar clear of stitching.

7 Fold back the shoulder seam allowance on the grown-on facing and press. Then fold the facing over the front edge of the collar.

8 Match the tailor's tacks in the collar and facing, and match the notches.

9 Machine from the center front to the tailor's tack at the shoulder point.


10 Trim the seam allowance.

Shoulder point

11 Turn through to the right side and press.

12 At the center back, turn under the seam allowance on the upper collar and hand stitch across the back neck with a flat fell or blind hem stitch.

FLAT ROUND COLLAR WITH A FULL FACING



Stand collar

LEVEL OF DIFFICULTY ***

Also called a mandarin collar, this collar stands upright around the neck. It is normally cut from a straight piece of fabric, with shaping at the center front edges. For a very close-fitting stand collar, the collar is cut with a slight curve.

1 Apply a fusible interfacing to the upper collar (see page 161). Insert any tailor's tacks as indicated on the pattern.



2 Pin the upper collar, interfacing side out, to the neckline of the garment, matching any notches and tailor's tacks at the center front edge.

3 Machine the upper collar to the neckline using a $\frac{1}{2}$ in (1.5 cm) seam allowance. Make sure the stitching stops at the tailor's tack at the front edge.



4 Reduce the seam allowance on the upper collar by half.

5 Clip through the seam allowances—this will allow the fabric to relax into shape when pressed later.

6 Working from the wrong side of the garment, turn in the center front edge as indicated by the pattern. This will leave the front edge of the collar sticking out from the garment.



7 Pin the under collar to the upper collar, right side to right side, along the top edge.

8 Machine the two pieces together using a $\frac{1}{2}$ in (1.5 cm) seam allowance.



9 At the center front, the reduced neck seam allowance needs to be pointing up into the collar, so that the machining attaching the two collar sections together goes over it. Be sure the machining is in line with the center front of the garment.

10 Reduce the seam allowance to half its width on the under collar side of the seam (the non-interfaced side).



11 Clip V shapes out of the seam allowance to reduce the bulk. Be careful not to cut through the stitching.

12 Press the seam as it has been stitched, and while warm turn to the right side.



13 Turn under the lower edge seam allowance on the under collar and baste in place around the neck edge.

14 Make sure the two leading front edges of the collar are symmetrical.



15 Use a flat fell stitch to secure the under collar at the neck edge.



Shawl collar

LEVEL OF DIFFICULTY ***

A shawl collar, which is a deep V-neck shape that combines both collar and revers in one, gives a flattering neckline that is often found on blouses and jackets. Although the collar looks complicated, it is straightforward to make. The under collar is usually part of the front of the garment.



Blouse collar with revers

LEVEL OF DIFFICULTY **

A blouse collar can have rounded or pointed center front edges, depending on the style of blouse chosen. A blouse collar forms a V neckline with revers. When constructing the collar, before fusing the interfacing to the upper collar, trim the corners of the interfacing to reduce bulk.


- 1** Construct the collar by placing the fabric right side to right side. Mark any pattern markings with tailor's tacks. Machine at $\frac{1}{2}$ in (1.5 cm).



- 2** Trim away the under collar side of the seam.


Interfacing removed from corners

- 3** Clip across the corners.



- 4** At the center back neck, snip through the seam allowance of just the upper collar at the tailor's tacks. Press this part of the seam open.

Sharp corners



- 5** Turn the collar through to the right side and press. The seam allowance on the back neck is pressed under between the clips.

- 6** Place the collar to the neck, matching the tailor's tacks. Pin to secure.



- 7** Baste in place through the double collar edges at the front and through the single layer collar at the back neck.

- 8** Place the front facing over the front part of the collar, matching notches and tailor's tacks.



- 9** Machine in place, stitching across the back neck at the same time. Match at the shoulder seams.

Sharp point in stitching at center front

- 10** Trim and layer the seam. Turn to the right side and press.

- 11** Turn under the raw edge of the upper collar at the back neck and baste in place, then hand stitch with a flat fell or blind hem stitch.



- 12** Press the collar and revers.

Rever

Two-piece shirt collar

LEVEL OF DIFFICULTY ***

A traditional-style shirt has a collar that consists of two pieces: a collar and a stand, both of which require interfacing. The stand fits close around the neck and the collar is attached to the stand. This type of collar is found on men's and ladies' shirts. On a man's shirt, the stand accommodates the tie.

- 1** Cut the upper and under collar. Apply interfacing to the upper collar.



- 2** Machine the upper and under collar together, right side to right side, stitching around the sides and the outside edge. Stitch a sharp point by pivoting at the corners.

- 3** Trim the seam allowance from the under collar.

- 4** Remove surplus fabric at the point.

- 5** Press the seam open, pressing the upper collar seam allowance down on to the collar. Clip as required.

- 6** The fabric at the point should not be bulky. If it is, remove more.



7 Turn the collar to the right side and press.

8 Top-stitch the sides and outside edge using the edge of the machine foot as a guide.



9 Construct the stand, applying interfacing to one side.

Collar fits between the tailor's tacks




10 Place the non-interfaced side of the collar to the interfaced side of the stand. Match the notches, then pin in place.

11 Machine the collar to the stand.

12 Place the stand to the shirt neck, matching the notches, and pin in place.

13 Baste the stand to the neckline. The seam allowance on the stand extends at the center front.



14 Pin the non-interfaced side of the collar stand to the neck edge, so that there is a collar stand on either side of the shirt.

15 Baste the collar stand to the neckline.



16 Reposition the stand so that the front edges come together right side to right side.

17 Machine along the neck edge and around the center front curve to the collar.



18 Trim away the non-interfaced side of the stand.

19 Remove surplus fabric from the corner.

20 Turn and press.


21 Bring the raw edge of the stand to the collar and turn under. Pin in place.



22 Secure this edge with a flat fell stitch.



23 Top-stitch the stand, if required. The stand fits snugly under the collar at the center front.









WAISTLINES, BELTS, AND TIE-BACKS

Bodice and skirt sections are often joined together at the waist. However, on some garments, a “waist” needs to be created to take a piece of elastic. A waist may be enhanced by making a matching belt. Curtain tie-backs are also covered in this section.

WAISTLINES

Waistlines can be formed where a bodice and skirt join together or at the waist edge of a skirt or pair of pants. Some waistlines are attached separately to the garment to create a feature and others are more discreet. They may be shaped to follow the contours of the body.




Directory of waistlines



Joining a fitted skirt to a bodice

LEVEL OF DIFFICULTY **



Many dresses feature a straight fitted skirt attached to a fitted dress bodice. When joining them together, it is important that the darts and seamlines on the bodice line up with those on the skirt.



Joining a gathered skirt to a bodice

LEVEL OF DIFFICULTY **

When attaching a gathered skirt to a fitted bodice, the gathers must be distributed evenly around the waist. If there are seams on the gathered skirt, these must be matched to the bodice seams and darts.








Making a casing at the waist edge

LEVEL OF DIFFICULTY **

An elasticated waist edge is featured on both skirts and pants and also at the waist edge on casual jackets. The casing can be made by using a deep waist seam or by attaching a facing. The facing will form a complete circle that will be attached to the waist edge.

USING A DEEP WAIST SEAM AS A CASING



USING A FACING AS A CASING

1 Cut the facing, and join the facing sections together at the side seams. Press open. Do not join the remaining seam, but press back the seam allowances.

2 Pin the facing to the raw edge of the garment.

3 Stitch the facing around the edge of the garment.

4 Layer the seam and press as stitched.

Gap where facing seam has been left open

5 Press the facing on to the wrong side of the garment.

6 Turn down the lower edge of the facing by $\frac{3}{8}$ in (1.5 cm).

7 Machine stitch down the facing at the folded edge, leaving a gap for the elastic to be inserted.

8 Insert the elastic into the facing and secure the ends.

Open seam on facing

Seam on garment

Applied casings

LEVEL OF DIFFICULTY **

Some elasticated waist edges will require the application of extra fabric to make a casing into which the elastic can be inserted. The casing may be applied to the inside or the outside of the garment. A quick way is to make the casing with bias binding. The casing can also be made from the same fabric as the garment or from a facing.

INTERNAL CASING

1 This type of casing is often used on a shirt-waisted dress or on a blouson-style jacket. Cut a strip of fabric on the straight of grain wide enough to accommodate your elastic and turnings.

2 Turn under the edge at one end by $\frac{3}{8}$ in (1.5 cm) and then the same along the sides. Press.

3 Mark the waist with a row of bastes.

4 Place the casing over the bastes with the finished short end toward the center front. Pin in place.

5 Machine to attach the casing to the waist.

6 Insert the elastic into the casing. Secure the elastic at both ends.

INTERNAL CASING USING BIAS BINDING

1 Be sure to use bias binding that will be wide enough to insert an elastic through after it has been stitched down. Apply the bias to the waistline and stitch at $\frac{1}{8}$ in (2 mm) from either edge.

2 Insert the elastic and knot the ends.

$\frac{3}{8}$ in (2 cm) wide bias binding

EXTERNAL CASING

1 Cut a strip of straight grain fabric $1\frac{3}{8}$ in (3.5 cm) wide x the waist measurement on the garment. Turn under all raw edges by $\frac{3}{8}$ in (5 mm) and press.

2 Place this casing over the garment waistline, with the short ends to the center front.

3 Machine in place along the long edges. Insert elastic to fit the waist.

Mock casings

LEVEL OF DIFFICULTY ***

There are several ways to construct mock casings. The simplest is to stitch on elastic at the waist. An alternative, if a bodice and skirt have a waist seam joining them together, is to insert elastic between the seam allowances. On many garments, there is elastic at the back only, in a partial casing, and a waistband interfacing at the front.

STITCHING ON ELASTIC TO MAKE A WAISTLINE

1 Cut a piece of elastic to the required length. Mark the waistline on the garment with a row of basting stitches.

2 Secure the elastic at one end with a pin.

3 Stretch the elastic across the fabric, pinning at regular intervals. The fabric will be loose under the elastic.

4 Secure the elastic at one end with a few machine stitches.

5 Place under the sewing machine and join the elastic to the fabric using a 3-step zigzag stitch, stretching the fabric and elastic together as you do so.

6 The elastic stitched in place.

7 On the right side there is a neat elasticated waistline.

CASING IN A WAIST SEAM ALLOWANCE




1 Join the fabric together using a $\frac{3}{4}$ in (2 cm) seam allowance.

2 Stitch again $\frac{3}{8}$ in (1.5 cm) from this stitching line, $\frac{3}{16}$ in (5 mm) from the raw edge.



3 Neaten the edge of the seam using a 3-thread serger stitch or a zigzag stitch.

4 Insert elastic into the casing that you have made, with the help of a safety pin.

ALTERNATIVE CASING USING A SEAM ALLOWANCE






PARTIAL CASING



A waist with a facing

LEVEL OF DIFFICULTY **




Many waistlines on skirts and pants are finished with a facing, which will follow the contours of the waist but will have had the dart shaping removed to make it smooth. A faced waistline always sits comfortably to the body. The facing is attached after all the main sections of the skirt or pants have been constructed.



Petersham-faced waist

LEVEL OF DIFFICULTY ***

Petersham is an alternative finish to a facing if you do not have enough fabric to cut a facing. Available in black and white, it is a stiff, ridged tape that is 1 in (2.5 cm) wide and curved—the tighter curve is the top edge. Like a facing, petersham is attached to the waist after the skirt or pants have been constructed.




Finishing the edge of a waistband


LEVEL OF DIFFICULTY *

One long edge of the waistband will be stitched to the garment waist. The other edge will need to be finished, to prevent fraying and reduce bulk inside.


TURNING UNDER



SEGER STITCHING



BIAS BINDING



Attaching a straight waistband

LEVEL OF DIFFICULTY **

A waistband is designed to fit snugly but not tight to the waist. Whether it is shaped or straight or slightly curved, it will be constructed and attached in a similar way. Every waistband will require a fusible interfacing to give it structure and support. Special waistband interfacings are available, usually featuring slot lines that will guide you where to fold the fabric. Make sure the slots on the outer edge correspond to a $\frac{5}{8}$ in (1.5 cm) seam allowance. If a specialist waistband fusible interfacing is not available, you can use a medium-weight fusible interfacing.

1 Cut the waistband and apply the interfacing. Neaten one long edge.

2 Pin the waistband to the skirt waist edge, right side to right side. Match the notches.

Wrong side of waistband

Neaten lower edge

Right side of fabric

3 Stitch the waistband to the waist edge using a $\frac{5}{8}$ in (1.5 cm) seam allowance. The waistband will extend beyond the zipper by $\frac{5}{8}$ in (1.5 cm) on the left and 2 in (5 cm) on the right.

4 Press the waistband away from the skirt.

Waistband extension to be finished

5 Fold the waistband along the crease in the interfacing, right side to right side. The neaten edge of the waistband should extend $\frac{5}{8}$ in (1.5 cm) below the stitching line.

6 Pin the end of the waistband in line with the center back.

7 On the right-hand back at the waist, fold the waistband in half, right side to right side. Trim and clip seam, press, turn and press again.

8 Extend the waist/skirt stitching line through the waistband and through the end. Trim and clip seam, press, turn and press again.

9 Turn the ends of the waistband to the right side. The extension on the waistband should be on the right-hand back.

10 Add your chosen fasteners.



11 To complete the waistband, stitch through the band to the skirt seam. This is known as "stitching in the ditch."



12 The finished straight waistband.




Ribbon-faced waistband

LEVEL OF DIFFICULTY ***

On a bulky fabric, you can replace the inner side of the waistband with a ribbon. This will not affect the structure and stability of the waistband, but will produce a less bulky finish. Use a grosgrain ribbon that is 1 in (2.5 cm) wide. Grosgrain ribbon looks like petersham (see page 177), but is ribbed and much softer.


1 Apply interfacing to the waistband as usual.



2 Press the waistband in half, wrong side to wrong side, to give a defined crease.


3 Working from the right side of the waistband, place the ribbon along one side of the crease approx. 1/8 in (3 mm) from the crease.

4 Machine in place along the upper edge only.



5 Using pinking shears, remove surplus waistband from behind the ribbon. (Pinking shears will give a softer line on bulky fabrics.)

6 Attach the waistband to the skirt as for a normal waistband (see opposite page).



7 Fold the ribbon side to the inside of the waistband and press.




8 To finish the lower edge, stitch in the ditch from the right side.

BELTS

A belt in a fabric that matches the garment can add the perfect finishing touch. Whether it be a soft tie belt or a stiff structured belt, it will be best if it has an interfacing of some kind—the firmer and more structured the belt, the firmer the interfacing should be. A belt will also need belt carriers to support it and prevent it from drooping.

Directory of belts and tie-backs



STRAIGHT BELT



OBI SASH



TIE BELT



RUCHED CURTAIN TIE-BACK




STRUCTURED CURTAIN TIE-BACK

Belt carriers






LEVEL OF DIFFICULTY ***

Belt carriers can be made from fabric strips and machined to the garment, or they can be made more simply from thread loops fashioned by hand stitching. Fabric carriers are designed to support a heavier belt.

HAND-STITCHED BELT LOOPS



MACHINE-STITCHED BELT CARRIERS



Reinforced straight belt

LEVEL OF DIFFICULTY ***

This is a straightforward way to make a belt to match a garment. It can be of any width as it is reinforced with a very firm fusible interfacing, such as a craft interfacing. If one layer of interfacing is not firm enough, try adding another layer. The interfacing should be cut along its length to avoid joins. To ensure that it is cut straight, use a rotary cutter on a self-healing mat.

1 Cut the interfacing to the dimensions of the finished belt. Cut the fabric to twice the width of the interfacing plus seam allowances.

2 Fold the fabric in half lengthwise and press to mark the center line. Place the interfacing along the crease, leaving the fabric longer at the pointed end of the interfacing.

3 Fuse the cut interfacing to the fabric.

4 At the center line on the pointed end, cut through to the side of the interfacing point.

5 Press the fabric edges over the interfacing. Press the point carefully.

6 Fold one long, raw edge of the belt under and press.

7 Press under the remaining edge to match and pin in place.

8 Baste along the pressed-under edges to sew them together.

9 Use short basting stitches around the point.

10 Machine stitch along both long sides of the belt, stitching on the right side of the fabric. Keep the machine stitching close to the edge— $\frac{1}{16}$ in (2 mm) from it. Make sure the stitching is accurate through the point.

11 Measure the positioning of the eyelets toward the pointed end of the belt.



12 Punch the hole for each eyelet with pliers.

13 Insert a $\frac{3}{16}$ in (4 mm) eyelet into the hole, working from the right side of the belt.



14 Change the heads in the pliers and squeeze the eyelets around the hole.

15 Insert one eyelet at the other end of the belt about 2 in (5 cm) from the end, placing it centrally on the right side of the belt.



16 Push the buckle prong through the eyelet.

17 Fold the surplus fabric over on itself under the buckle and pin.

18 Secure with a machine or hand stitch, then turn the belt over.



19 When the belt is placed around the waist, check that the fit is correct. Add extra eyelets if required.



Tie belt

LEVEL OF DIFFICULTY **

A tie belt is the easiest of all the belts to make. It can be any width and made of most fabrics, from cottons for summer dresses to satin and silks for bridal wear. Most tie belts will require a light to medium-weight interfacing for support. A fusible interfacing is the best choice as it will stay in place when tied repeatedly. If a very long tie belt is required, the belt can be joined at the center back.

1 Cut fabric for the belt, with a point at each end. Cut a fusible interfacing the same length, but half the width.

2 Place the interfacing on one half of the fabric on the wrong side and press to fuse.

Non-interfaced side

3 Fold the belt in half, right side to right side so the fusible is showing. Pin.

4 Stitch along all the raw edges using a $\frac{1}{2}$ in (1.5 cm) seam allowance. Remember to leave a gap of approx. 3 in (8 cm) at the center back to turn the belt through.

5 Layer the seam by removing half of the seam allowance on the fused side.

6 Remove the bulk from the corners.

7 Press the seam as stitched, then turn through while the fabric is still warm.

8 Once the belt has been turned to the right side, press the seam carefully so that it is on the very edge.

10 Wrap around the waist and tie as required.

9 Press the points carefully.

Obi sash

LEVEL OF DIFFICULTY ***

An obi sash is a variation of the traditional sash that is worn with a kimono. This type of sash has a stiffened center piece with softer ties that cross at the back and then wrap to the front and tie. If you are using a firm fabric such as silk dupion, satin, or heavy cotton, interfacing will not be required for the ties.

1 Make the ties first. Cut long strips of fabric of the required length and width.


2 Fold the ties lengthwise in half, right side to right side, and pin.

3 Stitch the long, raw edges together. Stitch across the angled end.

4 Trim the pointed corners.

5 Turn the tie ends to the right side and press.

6 Next make the center section. Cut out two shaped pieces of fabric and a matching piece of very firm fusible interfacing.



7 Fuse the interfacing to the wrong side of one piece of fabric. If one layer of interfacing does not make the fabric stiff enough, add another layer.

8 Center the tie ends to the short ends of the stiffened center piece on the right side. Machine stitch to secure, using a $\frac{1}{2}$ in (1 cm) seam allowance.



9 Place the non-stiffened fabric center piece on top, right side to right side, and pin around the edge.

10 Fold up and tuck the tie ends inside, between the two layers of fabric.

11 Machine stitch around the center section, leaving a gap of 3 in (8 cm) at the lower edge for turning through.

13 Clip the curved edges of the center section in the seam allowance.


12 Remove the surplus fabric from the corners.

14 Pull the tie ends through the gap at the lower edge.



15 Turn the center section through to the right side and press.

16 Hand stitch, using a flat fell or blind hem stitch, the gap at the lower edge.



17 The finished obi sash.

Curtain tie-backs


LEVEL OF DIFFICULTY **

Tie-backs are used to hold the drape of a curtain in position. Some are structured, with an interfacing, and follow a predetermined shape, while others are softer and more decorative. The construction of a tie-back is similar to that of a tie belt.

STRUCTURED TIE-BACK

1 Cut out two pieces of fabric for the tie-back. Use a heavy fusible interfacing and cut it to the same size as the fabric, minus the seam allowances of $\frac{1}{2}$ in (1.5 cm) on all sides.

2 Fuse the interfacing to the wrong side of one piece of fabric.



3 Pin the non-interfaced piece of fabric to the interfaced piece, right side to right side.


4 Stitch around the two pieces, taking a $\frac{1}{2}$ in (1.5 cm) seam allowance. The machining should follow the edge of the interfacing, but not go through it.

5 Leave a gap of $\frac{3}{4}$ in (8 cm) at the lower edge to turn through.




6 Remove the corners from the fabric layers.

7 Clip the concave curve with straight clips and the convex curve with V notches.




8 Turn the tie-back through to the right side.

9 Hand stitch the gap using a flat fell or blind hem stitch.



10 On the two short ends of the tie-back, sew on a curtain ring, using polyester all-purpose thread. Use a buttonhole stitch to secure it.



DECORATIVE RUCHED TIE-BACK

1 Cut a piece of curtain interlining 10 in (25 cm) wide and to the required tie-back length.

2 Roll up the interlining like a sausage, but not too tight, and pin in place.

3 Using a bold-colored thread, herringbone stitch the raw edge down to hold it in position. Make sure the rolled interlining is the same thickness throughout.

4 For the outer decorative layer, cut a piece of fabric 5 in (12 cm) wide and three times the required length.

5 Fold lengthwise in half, right side to right side.

6 Machine stitch the long raw edges together using a $\frac{3}{8}$ in (1 cm) seam allowance.

7 Stitch again, between the stitching line and the raw edge. The double stitching is for strength.

8 Turn the decorative top layer fabric through to the right side and press.

9 Tie the thread ends from the herringbone stitch on the interlining to a loop turner.

10 Using the loop turner, pull the interlining sausage through the decorative layer. This is difficult as it will stick. Work the decorative fabric gently down the interlining.

11 Ruche the decorative fabric up around the interlining, evening out the fabric with your fingers. Remove the loop turner.

12 Use a hand stitch about every $1\frac{1}{4}$ in (3 cm) to secure the ruching on the tie-back.

13 Sew on a curtain ring at each end, using a buttonhole stitch to secure the rings.





SLEEVES AND SLEEVE FINISHES

Sleeves come in all shapes and lengths, and form an important part of the design of a garment. They should always hang properly from the end of the wearer's shoulder, without wrinkles. The lower end of the sleeve is normally finished by means of a cuff or a facing.


SLEEVES

A few sleeves, such as the dolman, are cut as part of the garment, but most sleeves, including set-in and raglan, are made separately and then inserted into the armhole. Whichever type of sleeve is being inserted, always place it to the armhole and not the armhole to the sleeve—in other words, always work with the sleeve facing you.


Directory of sleeves



SET-IN SLEEVE (SHORT)



SET-IN SLEEVE (LONG)



SHORT TRUMPET SLEEVE



BISHOP SLEEVE




CAP SLEEVE




DOLMAN SLEEVE




KIMONO SLEEVE



GIGOT SLEEVE



PUFF SLEEVE








RAGLAN SLEEVE

Inserting a set-in sleeve

LEVEL OF DIFFICULTY ***

A set-in sleeve should feature a smooth sleeve head that fits on the end of your shoulder accurately. This is achieved by the use of ease stitches, which are long stitches used to tighten the fabric but not gather it.



Puff sleeve

LEVEL OF DIFFICULTY **

A sleeve that has a gathered sleeve head is referred to as a puff sleeve or gathered sleeve. It is one of the easiest sleeves to insert because the gathers take up any spare fabric.

- 1** Machine stitch the sleeve, right side to right side, using a $\frac{1}{2}$ in (1.5 cm) seam allowance. Press the seam open.



- 2** Between the sleeve notches, insert two rows of gather stitches, one row at $\frac{1}{8}$ in (1 cm) from the raw edge and the second row at $\frac{1}{2}$ in (1.3 cm).

- 3** Place the sleeve into the armhole, right side to right side.

- 4** Match the notches and the underarm seams.



- 5** Pull up the gathers to make the sleeve head fit the armhole.

- 6** Pin from the sleeve side.



- 7** Working with the sleeve uppermost, machine the sleeve to the armhole. Use a $\frac{1}{2}$ in (1.5 cm) seam allowance. Overlap machining at underarm to reinforce. Keep seam allowances open and flat.

- 8** Stitch around the sleeve seam again between the seam stitching and the raw edge.

- 9** Trim away the surplus fabric by $\frac{3}{16}$ in (5 mm).

- 10** Neaten the seam.




- 11** Turn right side out—all the gathers will be at the top of the sleeve.



Flat sleeve construction


LEVEL OF DIFFICULTY **

On shirts and children's clothes, sleeves are inserted flat prior to the side seams being constructed. This technique can be difficult on some fabrics, such as those firmly woven, because no ease stitches are used.



2 Match the notches and pin.

3 Stitch the sleeve to the armhole at a $\frac{3}{8}$ in (1.5 cm) seam allowance.



5 Neaten the seam.



7 Fold the garment and sleeve right side to right side. Match the underarm seams.


8 Stitch together with a $\frac{3}{8}$ in (1.5 cm) seam allowance.



Raglan sleeve

LEVEL OF DIFFICULTY **


A raglan sleeve can be constructed as a one-piece sleeve or a two-piece sleeve. The armhole seam on a raglan sleeve runs diagonally from the armhole to the neck.



2 Press the seam open.

Sleeve front

Sleeve back




4 Stitch together using a $\frac{3}{8}$ in (1.5 cm) seam allowance.

5 Press the seams open.




7 Machine the side seam of the garment and continue stitching down the sleeve.



Kimono sleeve

LEVEL OF DIFFICULTY **



A kimono sleeve is a very large, deep sleeve that is inserted on to a garment prior to its construction. Some kimono sleeves are cut with a curve and others are cut straight, but they are made the same way.



Dolman sleeve

LEVEL OF DIFFICULTY *






A dolman sleeve is cut as an extension to a garment. As the armhole is very loose, it is ideal for a coat or jacket. The dolman sleeve often has a raglan shoulder pad to define the shoulder end.



Dolman sleeve with a gusset

LEVEL OF DIFFICULTY ***




A dolman sleeve can be cut through, to give a tight sleeve. However a tight dolman sleeve will require an underarm gusset to allow movement. The gusset requires accurate stitching and marking if it is to be inserted correctly.



SLEEVE EDGE FINISHES

The lower edge of a sleeve has to be finished according to the style of the garment being made. Some sleeves are finished tight into the arm or wrist, while others may have a more decorative or functional finish.

Directory of sleeve edge finishes



Sleeve hems

LEVEL OF DIFFICULTY **

The simplest way to finish a sleeve is to make a small hem, which can be part of the sleeve or additional fabric that is attached to turn up. A self hem is where the edge of the sleeve is turned up on to itself. If there is insufficient fabric to turn up, a bias binding can be used to create the hem. You can use purchased bias binding or make your own bias strips.

SELF HEM

1 Mark the final length of the sleeve with a row of basting stitches.

Hem allowance

Seam pressed open

2 Remove the excess seam allowance in the hem area.

3 Turn up the hem along the basted line.

4 Match the seams. Pin in place.

5 Turn under the top edge of the hem allowance by $\frac{3}{8}$ in (1 cm) and pin.

6 Baste to secure.

7 Hand stitch the sleeve hem in place using a slip stitch. Use a seam allowance of $\frac{1}{8}$ in (3 mm).

Finished hem

BIAS-BOUND HEM

1 Mark the final length of the sleeve with a row of basting stitches.

2 Trim back the hem allowance to $\frac{3}{8}$ in (5 mm).

3 Cut a strip of $\frac{3}{8}$ in (2 cm) wide bias binding to the required length. Attach the bias to the sleeve, right side to right side.

4 Turn under the end of the bias, placing the fold of the bias to the sleeve seam.

5 Machine in place using a $\frac{3}{16}$ in (5 mm) seam allowance.

6 Press the seam allowance toward the bias.

Bias binding




Turned under end now on the top

7 Turn the bias to the inside of the sleeve and machine in place, stitching along the upper edge of the bias.


A casing on a sleeve edge

LEVEL OF DIFFICULTY **


A casing is often used on the edge of a sleeve to insert elastic into, which will allow you to gather the sleeve in a specific place. The casing may be grown-on, which means it is part of the sleeve, or it may be applied separately. The photographs below show an applied casing of bias binding.



4 Cut a length of elastic to fit your arm or wrist. Insert the elastic behind the bias binding and secure at one end by stitching through all layers.





6 To complete, join the sleeve seam, matching through the elastic and casing.



Elasticated edge with a heading

LEVEL OF DIFFICULTY **

This is an alternative method for making a ruffle or heading at the end of a sleeve, using a casing that is part of the sleeve.



Elasticated sleeve edge

LEVEL OF DIFFICULTY **

The ends of sleeves on workwear and children's clothes are often elasticated to produce a neat and functional finish. Elastic that is $\frac{1}{2}$ in (12 mm) or 1 in (25 mm) wide will be most suitable.

1 Make up the sleeve and press the seam open.



2 Work a row of basting stitches on the foldline of the hem.

3 Turn up $\frac{1}{4}$ in (6 mm) at the raw edge and press.



4 Turn again on to the basting line.

5 Machine to hold the turn-up in place, $\frac{1}{16}$ in (2 mm) from the folded edge. Leave a 1 in (3 cm) gap next to the seam allowance through which you will insert the elastic.

Gap to insert the elastic



6 Machine the bottom of the sleeve $\frac{1}{16}$ in (2 mm) from the edge, to give a neat finish. This will also help prevent the elastic from twisting.



7 Cut a piece of elastic to fit the arm or wrist and insert it into the sleeve end between the two rows of machining.

8 Secure the ends of the elastic together, stitching an X for strength.



9 Turn the sleeve through the armhole and check that the elasticated edge is even.



Sleeve edge with ruffle

LEVEL OF DIFFICULTY **

A ruffle at the end of a sleeve is a very feminine finish. It is used on a set-in sleeve that may or may not have a gathered sleeve head.

1 First, cut out the ruffle according to your pattern.

2 Neaten the outer edge of the ruffle with a 3-thread serger stitch or a zigzag stitch.

3 Turn the neaten edge $\frac{3}{8}$ in (1 cm) to the wrong side of the ruffle and machine in place.

4 Join the short ends of the ruffle together, right side to right side, using a $\frac{3}{8}$ in (1.5 cm) seam allowance.

5 Neaten the seam edge using your preferred method, then press the seam open.

6 Place the ruffle at the end of the sleeve, right side to right side, matching seams and notches.

7 Stretch the ruffle to fit, then pin in place.

8 Machine the ruffle to the sleeve around the sleeve edge, using a $\frac{3}{8}$ in (1.5 cm) seam allowance.

9 Neaten the seam edge, then press the seam open.

10 Press the seam toward the sleeve, then turn the sleeve through the armhole to the right side.

Faced sleeve edge

LEVEL OF DIFFICULTY **

Adding a facing to the end of a sleeve produces a very clean and bulk-free finish. This technique is particularly suitable for dress sleeves and sleeves on unlined jackets.

1 Apply a fusible interfacing to the facing.

2 Join the short ends of the facing together, right side to right side, then press the seam open.

3 Turn up one long edge of the facing by $\frac{3}{8}$ in (1 cm) and pin in place.

4 Machine the turned-up edge by $\frac{3}{8}$ in (1 cm) and press the folded edge flat.

5 Place the facing to the end of the sleeve, right side to right side, matching the seams together and with the raw edges of the facing and sleeve together.

6 Pin in place.

7 Trim the facing seam allowance down to half its width.

8 Press the whole seam allowance toward the facing. Use a seam roll to help the pressing.

9 Understitch the seam allowance to the facing.

10 Turn the facing through to the inside of the sleeve.


Completed facing

11 Press the sleeve edge on the right side.


CUFFS AND OPENINGS

A cuff and an opening are ways of producing a sleeve finish that will fit neatly around the wrist. The opening enables the hand to fit through the end of the sleeve, and it allows the sleeve to be rolled up. There are various types of cuffs—single or double, and with pointed or curved edges. All cuffs are interfaced, with the interfacing attached to the upper cuff. The upper cuff is sewn to the sleeve.


Directory of cuffs and openings




SINGLE CUFF WITH FACED OPENING




SINGLE CUFF WITH PLACKET OPENING



SINGLE CUFF WITH BOUND OPENING



DOUBLE CUFF



SHIRT CUFF

One-piece cuff

LEVEL OF DIFFICULTY **

- 1** Apply fusible interfacing to the half of the cuff that will be the upper cuff.



- 2** Turn under a seam allowance on the non-interfaced side and baste to secure.

A one-piece cuff is cut out from the fabric in one piece, and in most cases only half of it is interfaced. The exception is the one-piece double cuff (see page 209).

- 3** Fold the cuff in half, right side to right side.

- 4** Machine stitch down the two short ends.

- 5** Layer the seam by trimming one edge, and clip the corners.

Seam allowance free on interfaced side of cuff

Seam allowance ready to stitch on to sleeve

- 6** Turn the cuff through to the right side and press.

Two-piece cuff

LEVEL OF DIFFICULTY **

- 1** Apply fusible interfacing to the upper cuff.



- 2** Turn under a seam allowance on the under cuff and baste in place.

- 3** Place the upper and under cuff together, right side to right side.

Some cuffs are cut in two pieces: an upper cuff and an under cuff. The upper cuff piece is interfaced.

- 4** Machine stitch the two short ends together. Also machine together along the lower edge.

Seam allowance on upper cuff free

- 5** Layer the seam and clip the corner.


- 6** Turn the cuff through to the right side and press. The seam allowance at the top is ready to be stitched to the sleeve.

Faced opening


LEVEL OF DIFFICULTY **

Adding a facing to the area of the sleeve where the opening is to be is a neat method of finishing. This type of opening is appropriate to use with a one-piece cuff.

1 Turn under the long edges and one short edge on the facing by about $\frac{1}{8}$ in (3 mm). Machine stitch to secure.



2 Place the right side of the facing to the right side of the sleeve at the appropriate sleeve markings.



3 Stitch vertically up the center of the facing. Take one stitch across the top and then stitch straight down the other side. Keep a distance of about $\frac{1}{4}$ in (6 mm) between the stitching lines at the raw edge.

4 Slash between the stitching lines.




5 Snip with small scissors into the corners.

6 Turn the facing to the wrong side of the sleeve and press.







7 The finished opening on the right side.



Bound opening

LEVEL OF DIFFICULTY **

On a fabric that frays badly or a sleeve that may get a great deal of wear, a strong bound opening is a good idea. It involves binding a slash in the sleeve with a matching bias strip.




Shirt sleeve placket

LEVEL OF DIFFICULTY ***


This is the opening that is found on the sleeves of men's shirts and tailored ladies' shirts. It looks complicated, but is straightforward if you take it one step at a time.

1 Cut out the placket and mark the pattern dots with tailor's tacks. Only these four tailor's tacks are required.




2 Place the placket to the shirt sleeve, right side of the placket to the wrong side of the sleeve, matching the tailor's tacks.

3 Pin in place.




4 Machine a rectangular box, joining the tailor's tacks together. Make sure the rows of stitching are parallel. Remove tailor's tacks.




5 Slash through the placket and sleeve straight down the center, between the rows of stitching.

6 Slash into the corners of the rectangle.



7 Open up the placket to the right side of the fabric and press. You will have a rectangular gap with sharp corners.



8 Fold back the long edge of the shorter side of the placket.

9 Place the folded edge on top of the machine stitching and pin in place.




10 Machine the folded edge with a $\frac{1}{16}$ in (2 mm) seam allowance. Stop the machining at the top of the gap.




11 Fold the other side of the placket across the shorter side.

12 Press under the long edge. Fold back so that the pressed-under edge is on the machining line. Pin in place.



13 Fold under the top pointed end, following the cut edge, and press.

14 Machine the long folded edge in place. Make sure the underside of the placket is not caught in the stitching.



15 Continue the machining around the point.

16 Stitch an X through the point.



17 Pull all the ends of the machining threads through to the reverse and tie off.



18 On the right side, the completed placket will be neatly stitched.



Attaching a cuff

LEVEL OF DIFFICULTY ***

There are various types of cuff that can be attached to sleeve openings. The one-piece lapped cuff works well with a bound or faced opening. A two-piece shirt cuff is usually on a sleeve with a placket opening, but works equally well on a bound opening. The double cuff, or French cuff, is for men's dress shirts and tailored shirts for both ladies and men, and may be cut in one or two sections. It is usually found with a placket or bound opening.

LAPPED CUFF

1 Apply fusible interfacing to the upper half of the cuff. Pin the interfaced end of the cuff to the sleeve end, right side to right side.

Seam allowance extending

2 Machine the cuff to the sleeve using a $\frac{3}{8}$ in (1.5 cm) seam allowance.

3 Trim the sleeve side of the seam down by half. Press the seam toward the cuff.

Overlap

4 Fold the non-interfaced edge of the cuff over to the wrong side by $\frac{3}{8}$ in (1.5 cm) and press along the non-attached edge.

5 Fold the cuff to itself, right side to right side, so the folded side of the cuff comes to the sleeve-to-cuff seamline.

6 Stitch the one short end in line with the opening.

7 Stitch the other short end along from the sleeve-to-cuff seam and then down the cuff.

8 Remove the corners. Press the seams open.

9 Turn the cuff to the right side. Push the corners out to points.

10 On the inside, hand stitch the folded edge (using a flat fell or blind hem stitch) to finish.

11 Make a buttonhole on the upper side of the cuff.

12 Sew a button on the underside of the cuff.

SHIRT CUFF

1 Apply fusible interfacing to the upper cuff. Place it to the sleeve end, right side to right side, with a seam allowance extending at either end. Pin in place.



3 Place the right side of the under cuff to the right side of the upper cuff. Machine together around three sides, stitching in line with the sleeve opening.

4 Trim down the under cuff side of the seam.

5 Remove bulk from the corners. Press.

6 Turn the cuff to the right side and press.

7 Turn under the raw edge of the under cuff and place to the end of the sleeve. With this type of sleeve, the edge of the cuff is machined in place.

8 Add buttonholes to the upper cuff and attach buttons to the under cuff.



DOUBLE CUFF

1 Apply interfacing to the whole of the cuff. Attach the cuff to the sleeve end, right side to right side, using a $\frac{3}{8}$ in (1.5 cm) seam allowance.



2 Fold the cuff back on to itself, right side to right side.

3 Machine stitch the two sides in line with the sleeve opening.

4 Trim the bulk from the seams and corners.




5 Press, then turn the cuff through to the right side.

6 Fold the cuff up in half so that it is doubled. Press.

7 Hand stitch inside to finish the other edge of the cuff.

8 Insert a buttonhole through the top two layers of the cuff and sew a button on to the under cuff.








POCKETS

Pockets can be functional or just for show, and are essential on some items of clothing. Making a pocket requires a little patience, but the finished result is well worth it.


POCKETS

Pockets come in lots of shapes and formats. Some, such as patch pockets, paper bag pockets, and jettied pockets with a flap, are external and can be decorative, while others, including front hip pockets, are more discreet and hidden from view. They can be made from the same fabric as the garment or from a contrasting fabric. Whether casual or tailored, all pockets are functional.


Directory of pockets




PATCH POCKET




PAPER BAG POCKET




KANGAROO POCKET



FRONT HIP POCKET



IN-SEAM POCKET







WELT POCKET

Unlined patch pocket

LEVEL OF DIFFICULTY **


An unlined patch pocket is one of the most popular types of pocket. It can be found on garments of all kinds and be made from a wide variety of fabrics. On lightweight fabrics, such as used for a shirt pocket, interfacing is not required, but on medium and heavier fabrics, it is advisable to apply a fusible interfacing.



Self-lined patch pocket

LEVEL OF DIFFICULTY **

If a patch pocket is to be self-lined, it needs to be cut with the top edge of the pocket on a fold. Like an unlined pocket, if you are using a lightweight fabric, an interfacing may not be required, whereas for medium-weight fabrics, a fusible interfacing is advisable. A self-lined patch pocket is not suitable for heavy fabrics.



2 Fold the pocket in half, right side to right side. Pin to secure.

3 Machine around the three open sides of the pocket. Leave a gap of 1 in (3 cm) for turning through.

4 Remove bulk from the corners by trimming.

5 Trim one side of the seam allowance down to half its width.

6 Use pinking shears to trim the corners.

7 Turn the pocket through the gap to the right side. Press.

8 Hand stitch the gap (using a flat fell or blind hem stitch) in the seam. The pocket is now ready to be attached.

Lined patch pocket

LEVEL OF DIFFICULTY **

If a self-lined patch pocket is likely to be too bulky, then a lined pocket is the answer. It is advisable to interface the pocket fabric.

1 Cut the pocket fabric and apply interfacing. Cut the lining fabric. The lining will be shorter than the pocket fabric.



2 Place the lining top edge to the upper edge of the pocket and machine together. Leave a 1 in (3 cm) gap in the seam for turning through.

3 Press the pocket-to-lining seam open.



4 Bring the bottom edges of the pocket together.


5 Pin through the corners and sides.

6 Stitch around the other three open sides of the pocket to attach the lining to the pocket fabric.

7 Remove the corners.



8 Use pinking shears to trim the curves.



9 Turn through the gap left in the seam to the right side. Press.

10 Hand stitch the gap using a flat fell or blind hem stitch.



11 The lined patch pocket is ready to be attached.

Square patch pocket

LEVEL OF DIFFICULTY **

It is possible to have a patch pocket with square corners. This requires mitering the corners to reduce the bulk. Use a fusible interfacing on medium-weight fabrics.


1 Cut the pocket and apply interfacing, if needed. Neaten the upper edge of the pocket with serger or zigzag stitching.

2 Fold over the upper edge and stitch down the sides.

3 Fold in the other three edges and press to crease.

4 Remove the top corners.

5 Fold in the bottom corners, then fold across these to give creases for the miters.



6 Stitch the crease lines together in each bottom corner to miter it.

7 Cut off the surplus fabric, then press the corner seam open with the toe of the iron.

8 Turn the edges of the pocket to the wrong side. Press entire pocket turned to the right side.

Wrong side of fabric

Flat mitered corners




9 The finished pocket is now ready to be attached.



Attaching a patch pocket


LEVEL OF DIFFICULTY **

To attach a pocket well, accurate pattern marking is essential. It is best to do this by means of tailor's tacks or even trace basting. If you are using a checker or striped fabric, the pocket fabric must align with the checkers or stripes on the garment.




1 Mark the pocket placement lines on the garment with tailor's tacks.

2 Take the completed pocket and place it to the fabric, matching the corners with the tailor's tacks. Pin in position.



3 To make sure the pocket remains in the correct position, baste around the edge along the sides and bottom. Keep the basting stitches close to the finished edge of the pocket.



4 Machine stitch approx $\frac{1}{32}$ in (1 mm) from the edge of the pocket.

5 Remove the basting stitches. Press.




6 Alternatively, the pocket can be hand stitched in place, using a slip hem stitch into the underside of the pocket seam. Do not pull on the thread too tightly or the pocket will wrinkle.

Reinforcing pocket corners

LEVEL OF DIFFICULTY **

On any patch pocket, it is essential to reinforce the upper corners as these take all the strain when the pocket is being used. There are several ways to do this, some of which are quite decorative.

REVERSE STITCH



1 Reinforce the corner with a reverse stitch. Make sure the stitches lie on top of one another.

2 Pull the threads to the reverse to tie off.


DIAGONAL STITCH



1 This is a technique used primarily on shirts. When machining the pocket in place, stitch along horizontally for four stitches.

2 Turn and stitch diagonally back to the side, to create a triangular shape in the corner.

ZIGZAG STITCH



1 Using a small zigzag stitch, width 1.0 and length 1.0, stitch diagonally across the corner.

2 Make a feature of this stitch by using a thread in a contrasting color.

PARALLEL ZIGZAG STITCH



1 Place a patch on the wrong side of the garment, behind the pocket corner, to stitch into for strength.

2 Using a small zigzag stitch, width 1.0 and length 1.0, machine a short vertical line next to the straight stitching.

Paper bag pocket

LEVEL OF DIFFICULTY ***

This pocket is so-named because it resembles a paper bag. It is found on men's and women's casual wear. The pocket is attached to the garment with a gusset, which is a straight strip of fabric. A paper bag pocket is best made in a light or medium-weight fabric.

1 First neaten the upper edge of the pocket. Fold it over twice, making a double hem. Stitch along the edge close to the fold.



2 Place the gusset to the outer edge of the pocket, right side to right side.

3 Fold under the ends of the gusset and match the ends to the edge of the pocket.

4 Stitch the gusset to the pocket along the sides and bottom.

5 Clip the seam allowance in the curves.



6 Turn under the raw edge of the gusset. Miter the corners. Baste to secure.




7 Place the basted edge to the garment. Match the edge to the tailor-tack markings on the garment. Pin.



8 Machine the edge of the gusset to the garment. Stitch close to the folded edge.

9 Remove the basting.



10 At the top edge, pleat the gusset under the pocket and place the top corner of the pocket and gusset together.

11 Stitch diagonally across the upper corners through the pocket, gusset, and garment. Leave the lower curved edges loose.




Making a pocket flap

LEVEL OF DIFFICULTY **

On some styles of garment, there is no pocket, just a flap for decorative purposes. The flap is sewn where the pocket would be, but there is no opening under the flap. This is to reduce the bulk that would arise from having the rest of the pocket.

1 The flap consists of two pieces—a piece of lining and a piece of interfaced fabric. Place the two pieces together, right side to right side.



2 Match the tailor's tacks, then pin to secure.


Smooth curve stitched

3 Stitch the pocket flap together along three sides, using a $\frac{1}{8}$ in (1 cm) seam allowance. Stitch through the tailor's tacks. Leave the upper edge open.



4 Layer the seam allowance, trimming away the lining side.


5 Remove the fabric from the point.



6 Use pinking shears to reduce the bulk through the curve. Press.

7 Turn the flap through to the right side. Push out the point.

8 Press the lining toward the back so that it does not show. Press a smooth curve.



9 Stitch across the upper open edge to hold together.

10 Place the flap to the garment, right side to right side. Match the edges of the flaps to the tailor's tacks on the garment.

11 Machine in place over the stitching line, holding the gap at the upper edge together.



12 Reduce the seam allowance by half. Press.

13 Press the flap into place. Do not pull too tight.






14 Top-stitch across the upper edge to secure.



Welt pocket

LEVEL OF DIFFICULTY ***

A welt pocket features a small, straight flap that faces upward on a garment, with the pocket opening behind the flap. This kind of pocket is found on vests and is the usual breast pocket on men's jackets, as well as being used on coats.



13 The finished welt pocket on the right side.

Jetted pocket with a flap

LEVEL OF DIFFICULTY ****

This type of pocket is found on tailored jackets and coats and men's wear. It is straightforward to make. The main components are the welts (the strips that make the edges of the pocket), the flap, and the lining that makes the pocket bag.

- 1** First make the upper welt.
Apply fusible interfacing to the wrong side.



- 2** Fold in half lengthwise, wrong side to wrong side. Baste down the center to secure.


- 3** Next, make the pocket flap.
Apply fusible interfacing to the wrong side of the fabric.



- 4** Place the right side of the lining to the right side of the flap. Pin, then machine around three sides, leaving the top edge open. Press.

- 5** Remove the fabric from the bottom corners.

- 6** Turn the flap through to the right side. Press. Make sure the lining does not show on the right side.



- 7** If you like, top-stitch the flap around the three sides.



- 8** On the welt, trim the raw edge of the seam allowance down to half its width.


- 9** Place the welt to the right side of the pocket. Align the raw edges. Make sure the welt overhangs the flap by equal amounts at each end.



- 10** Machine together through the center of the welt.

- 11** Place the right side of the welt and flap to the right side of the garment. Match the ends of the flap to the upper tailor's tacks on the garment. Pin in place.


- 12** Machine to the lining along the stitching line that is holding the welt and flap together.



- 13** Make up the lower welt in the same fabric as the upper welt.


- 14** Place the lower welt to the garment below the upper welt and flap.





- 15** Machine stitch in place. Make sure the two rows of stitching are exactly the same length. Also make sure the stitching lines are parallel.



- 16** Take the lining and press in half, right side to right side, matching the tailor's tacks, to produce a center crease.

- 17** Place the right side of the lining over the welt and flaps, matching the tailor's tacks. The crease line should be sitting between the two welts. Pin in place.








In-seam pocket





LEVEL OF DIFFICULTY **

In pants and skirts, the pocket is sometimes disguised in the seam line. There are two ways of making an in-seam pocket, either by adding a separate pocket shape or by the pocket shape being cut as part of the main fabric.

SEPARATE IN-SEAM POCKET



ALL-IN-ONE IN-SEAM POCKET




Front hip pocket

LEVEL OF DIFFICULTY **

On many pants and casual skirts, the pocket is placed on the hipline. It can be low on the hipline or cut quite high as on jeans. The construction is the same for all types of hip pockets. When inserted at an angle, hip pockets can slim the figure.

1 Apply a piece of fusible tape on the garment along the line of the pocket.



2 Place the pocket lining to the front of the garment, right side to right side. Match any notches that are on the seam. Pin in place.



3 Machine the lining in place taking a $\frac{5}{8}$ in (1.5 cm) seam allowance.

4 Trim the lining side of the seam allowance down to half its width.

5 Open out the pocket and press the seam toward the lining.




6 Turn the lining to the inside. Press so that the lining is not visible on the outside.

7 Top-stitch $\frac{3}{16}$ in (5 mm) from the edge.



8 On the right side of the garment, pin the pocket bag securely along the pocket opening.



9 Take the side front section that incorporates the pocket bag and place to the lining pocket section, right side to right side. Match any seams and tailor's tacks. Pin in place.

Wrong side of garment



10 Machine the pocket bag together using a $\frac{5}{8}$ in (1.5 cm) seam allowance. Press.



11 Neaten the raw edges of the seam allowance around the pocket.

12 Neaten the side seam allowance, stitching from the top down. Make sure that the fabric lies flat where it joins on to the side seam.



13 The angled front hip pocket from the right side.



Kangaroo pocket

LEVEL OF DIFFICULTY **

This is a variation on a patch pocket. It is a large pocket that is often found on aprons and the front of children's pinafore dresses. A half version of this pocket also features on casual jackets.

1 Neaten all the edges of the pocket.



2 Tie off the ends of the neatenings at the corners.

3 Turn under the curved edges of the pocket, by $\frac{3}{8}$ in (1.5 cm), to the wrong side. These will be the two pocket openings.



4 Press the curve and machine to secure.



5 Turn under all the remaining edges of the pocket to the wrong side. If the fabric is bulky, miter the corners. Press in place.

6 Place the pocket to the garment, wrong side of the pocket to right side of the garment. Make sure the pocket is sitting flat and straight. Pin in place.



9 Reinforce the corners of the pocket with a diagonal zigzag stitch (see page 216).


10 If required, stitch one or two vertical lines down the center of the pocket, to divide into two pockets. Press.



7 Stitch the pocket along the upper edge.

8 Stitch the short straight sides and lower edge of the pocket. Press.








HEMS AND EDGES

The lower edge of a garment or of a curtain or other soft furnishing is normally finished with a hem. This is to give not only a neat finish, but also to provide weight at the lower edge so that the garment or curtain hangs well.


HEMS AND EDGES

The edge of a piece of fabric can be finished with a hem—which is normally used on garments—or with a decorative edge, which is used for crafts and soft furnishings as well as garments. Sometimes the style of what is being constructed dictates the finish that is used, and sometimes it is the fabric.


Directory of hems




SINGLE TURN HEM




ROLLED HEM



DOUBLE TURN HEM



BIAS-BOUND HEM



FACED HEM

Marking a hemline

On a garment such as a skirt or a dress, it is important that the hemline is level all around. Even if the fabric has been cut straight, some styles of skirt—such as A-line or circular—will “drop,” which means that the hem edge is longer in some places. This is due to the fabric stretching where it is not on the straight of the grain. Poor posture will also cause a hem to hang unevenly.

USING A RULER

1 You'll need a helper for this method. Put on the skirt or dress (without shoes). With the end of the ruler on the floor, measure straight up on to the skirt.

2 Use pins to mark where the crease line of the hem should be. Mark the hemline all the way around to the same point on the ruler.




USING A DRESSMAKER'S DUMMY

1 Adjust the dummy to your height and measurements. Place the skirt or dress on the dummy.

2 Using the hem marker on the stand, mark the crease line of the hem. The hem marker will hold the fabric either side of the hemline.

3 Slide a pin through the slot in the marker, then gently release the marker.




Turning up a straight hem

LEVEL OF DIFFICULTY *

1 Gently press the crease line of the hem with the iron. Don't press too hard as you do not want a sharp crease.


2 Trim the seam allowance back to reduce the bulk. If wished, neaten the raw edge.



Once the crease line for the hem has been marked by the pins, you need to trim the hem allowance to a reasonable amount. Most straight hems are about 1½ in (4 cm) deep.

3 Turn up the hem at the crease. Match the seams together.

4 Baste the hem into position close to the crease line. The hem is now ready to be stitched in place by hand or machine.



Turning up a curved hem

LEVEL OF DIFFICULTY **

When the hem on a shaped skirt is turned up, it will be fuller at the upper edge. This fullness will need to be eased out before the hem is stitched.


Wrong side

1 Mark the hemline, placing the pins vertically to avoid squashing the fullness out of the upper raw edge.

2 Baste the hem into position close to the crease line. Remove the pins.



3 Make a row of long machine stitches, length 5.0, close to the raw upper edge of the turned-up hem.



4 Pull on one of the threads of the long stitches to tighten the fabric and ease out the fullness.

5 Use the steam iron to shrink out the remainder of the fullness. The hem is now ready to be stitched in place by hand or machine.



Hand-stitched hems

LEVEL OF DIFFICULTY *

One of the most popular ways to secure a hem edge is by hand. Hand stitching is discreet and, if a fine hand sewing needle is used, the stitching should not show on the right side of the work.

TIPS FOR SEWING HEMS BY HAND

1 Always use a single thread in the needle—a polyester all-purpose thread is ideal for hemming.

2 Once the raw edge of the hem allowance has been neaten by one of the methods below, secure it using a slip hem stitch. For this, take half of the stitch into the neaten edge and the other half into the wrong side of the garment fabric.

3 Start and finish the hand stitching with a double stitch, not a knot, because knots will catch and pull the hem down.

4 It is a good idea to take a small back stitch every 4 in (10 cm) or so to make sure that if the hem does come loose in one place, it will not all unravel.

CLEAN FINISH

1 This is suitable for fine and lightweight fabrics. Turn the raw edge of the hem allowance to itself, wrong side to wrong side. Baste the edge and then machine.

2 Lightly press the hem into position.

3 Baste the hem in place.

4 Roll the edge stitching back and stitch underneath it.

5 Using a small slip hem stitch, secure the edge of the hem to the wrong side of the fabric. Roll the edge back into place.

6 Remove the basting and press lightly.

SERGING FINISH

1 Using a 3-thread serger stitch, stitch along the raw edge of the hem allowance.

2 Gently press the hem up into position and baste close to the crease.

3 Roll back the serged edge. Hand stitch to the wrong side of the fabric using a slip hem stitch.

4 Press carefully to prevent the serging from being imprinted through to the right side.

BIAS-BOUND FINISH

1 This is a good finish for fabrics that fray or that are bulky. Turn up the hem on to the wrong side of the garment and baste close to the crease line.

2 Pin the bias binding to the raw edge of the hem allowance.


3 Open out the crease in the bias and stitch along the crease line, keeping the raw edges level.

4 Turn down the bias over the raw edge and press.

5 Using a slip hem stitch, join the edge of the bias to the wrong side of the fabric. Remove the basting and press lightly.


ZIGZAG FINISH

1 Use this to neaten the edge of the hem on fabrics that do not fray too badly. Set the sewing machine to a zigzag stitch, width 4.0 and length 3.0. Machine along the raw edge. Trim the fabric edge back to the zigzag stitch.



2 Turn the hem on to the wrong side of the garment and baste in place close to the crease line.


3 Fold back the zigzag-stitched edge. Using a slip hem stitch, stitch the hem into place.



4 Roll the edge back into position. Remove the basting and lightly press.


PINKED FINISH

1 Pinking shears can give an excellent hem finish on difficult fabrics such as rayon or georgette. Machine a row of straight stitching along the raw edge, $\frac{3}{8}$ in (1 cm) from the edge. Pink the raw edge.



2 Turn up the hem to the wrong side of the garment and baste in place close to the crease line.


3 Fold back the edge along the machine stitching line and hand stitch the hem in place with a slip hem stitch.



4 Roll the hem edge back into place. Remove the basting and lightly press.

CURVED HEM FINISH

1 With a curved hem on a cotton or firm fabric, it is important that any fullness does not bulge on to the right side. Prior to turning up the hem into position, zigzag the raw edge, using stitch width 4.0 and stitch length 3.0.




2 Machine a row of straight stitching $\frac{3}{8}$ in (3 mm) below the zigzag stitching, using stitch length 5.0.

3 Pin the hem into position, placing the pins vertically.

4 Baste the hem into position close to the crease line.

5 Pull on the straight stitching to tighten the fabric.



6 Roll the zigzagged edge back to the straight stitching line and hand stitch the hem in place using a slip hem stitch. Remove the basting and press lightly.


Machined hems

LEVEL OF DIFFICULTY *

On many occasions, the hem or edge of a garment or other item is turned up and secured using the sewing machine. It can be stitched with a straight stitch, a zigzag stitch, or a blind hem stitch. Hems can also be made on the serger.

SINGLE TURN HEM

1 This is a popular technique. Turn up the hem to the wrong side of the work. Press in place.



2 Machine with a straight stitch close to the hem edge.




BLIND HEM STITCH

1 This is a single turn hem that is secured using the blind hem stitch on the machine. Neaten the raw edge of the fabric (here a serged finish has been used).

2 Fold the fabric as indicated for your machine (consult your instruction book). Pin, but not too close to the fold.

3 Using the blind hem foot and the blind hem stitch, secure the hem. The stitch line should be just below the neaten edge.

4 Press lightly on the right side.





DOUBLE TURN HEM

1 This hem will add weight at the edge. Fold up the raw edge of the fabric once and then fold again.

2 Press and pin in place.



3 Machine using a straight stitch, close to folded edge.



Hems on difficult fabrics

LEVEL OF DIFFICULTY **

Some very fine fabrics or fabrics that fray badly require more thought when a hem is to be made. This technique works very well on delicate fabrics.




Rolled hems

LEVEL OF DIFFICULTY **

A rolled hem is used on lightweight fabrics. It is often found on soft furnishings as well as garments. To make it, the fabric is rolled to the wrong side by using the rolled hem foot on the sewing machine.

STRAIGHT-STITCHED ROLLED HEM




ZIGZAG-STITCHED ROLLED HEM



SERGER ROLLED HEM






MANUAL ROLLED HEM



Machined curtain hems

LEVEL OF DIFFICULTY *




Curtains have hems at the bottom edge as well as at the sides. The hem at the bottom is treated differently from the side hems, using different techniques, although both types of hems are folded twice. The hems can be stitched using either machine or hand methods.



Hand-stitched curtain hems

LEVEL OF DIFFICULTY *


Hand stitching is used on heavier curtain fabrics or where you do not want a machine stitch to show on the right side. Everything is pressed in place first.



Mitered corners

LEVEL OF DIFFICULTY **

At the bottom corners of curtains, where the bottom and side hems meet, the fabric is folded at an angle. This is called a miter. By pressing the miter with the iron and then unfolding it, you can use the crease lines that have been formed as a guide for removing surplus fabric to reduce bulk. For lined curtains, where the lining is constructed separately, the side and bottom hems are machined in place. The same mitering technique is used for both curtains and linings.



Weighting curtains

LEVEL OF DIFFICULTY *

A weight is often inserted into the bottom hem of a curtain at the corners, to hold the curtain in place and make it hang properly. Specialist weights can be purchased, although a heavy coin can work just as well.




Hems on stretch knits

LEVEL OF DIFFICULTY **

When making a garment with a stretch knit, the hem will need to stretch as well. There are two methods for stitching the hem on stretch knits, and the one you use depends on whether the fabric will run or not when it is cut.

FABRIC THAT RUNS

1 Neaten the raw edge using a 3-thread serger stitch. If no serger is available, use a zigzag stitch on the sewing machine.



4 Insert a twin needle into the sewing machine and thread the machine with two threads.



FABRIC THAT DOES NOT RUN

1 Insert the twin needle into the machine and thread the machine with two threads.

2 Turn up the hem to the wrong side and baste to hold in place.

3 Machine the hem in position.



4 Trim the raw edge back to within $\frac{1}{8}$ in (3 mm) of the stitching on the wrong side.

Faced hem


LEVEL OF DIFFICULTY **

A faced hem is used on garments made from fabrics that may be too bulky to turn up without the hem showing, or on napped fabrics that may catch or ride up when they are worn. A faced hem is also used if there is not enough fabric to turn up to make a hem.

1 Cut a bias strip of lining fabric 4 in (10 cm) wide to make a facing. Join the strips together until there is enough to go all around the hem.

2 Baste under $\frac{3}{8}$ in (1 cm) along one long edge.

3 Pin the edge that has not been turned under to the lower edge of the garment, right side to right side.



4 Machine the bias facing in place. Use the edge of the machine foot as a guide to the seam width.

5 Press the seam as stitched.



6 Open out the bias facing. Press the seam down on to the bias.

7 Roll the bias facing to the wrong side of the garment. Make sure the seam is not on the crease line but shows on the wrong side.




8 Using a herringbone stitch, stitch the folded edge of the bias strip in place.




Decorative faced hem

LEVEL OF DIFFICULTY ***

If the edge of a garment, blind, cushion, or other item is to have a decorative effect, such as points or scallops (as shown here), a faced hem is used.




1 Make a template for the finished shape required. Use a cup or glass to draw around, to get a uniform scallop shape. Add your seam allowance before tracing onto the fabric.



4 Place the template on the facing and use a marker or chalk pencil to draw the shaped hem. A seam allowance of $\frac{3}{8}$ in (1.5 cm) is required between the lower edge of the template and the raw edge.


2 Cut a facing piece of fabric 4 in (10 cm) wide. Neaten one long edge with the serger or a zigzag stitch.

3 Pin the facing to the hem edge, right side to right side.



5 Stitch around the outline that you have drawn on to the fabric. Take one straight stitch between each scallop.

6 Working from the wrong side, trim close to the machine-stitching with pinking shears. Clip close into the machining at the top of the curves.




7 Turn through to the right side. Press the fabric as it is being turned, because you can work warm fabric into the required shape.

8 If required, secure the facing on each seam.

Fused hem


LEVEL OF DIFFICULTY *

A fused hem is useful for a fabric that is difficult to hand stitch, as well as for an emergency hem repair. It uses a fusible web that has a fusible adhesive on both sides.




1 Turn up the hem to the wrong side of the fabric. Press. Baste the hem in place close to the crease line.

2 Neaten the raw edge with a serger or zigzag stitch.



3 Insert the fusible hemming tape between the hem and the wrong side of the garment. Make sure the tape sits just below the serger or zigzag stitch. Pin the tape in place.





4 Cover the hem allowance with a pressing cloth and, using a steam iron, press the edge of the hem to fuse the tape to the fabric. Once cool the hem will be stuck in place. Remove the basting stitches and pins.

Bias-bound hems





LEVEL OF DIFFICULTY **

A bias-bound hem will give a narrow decorative edge to a garment or an item of home furnishing. It is particularly useful for curved shapes, to finish them neatly and securely. On a chunky or bulky fabric, a double bias is used so that it will be more substantial and hold its shape better. A double bias is also used on sheer fabrics as there will be no visible raw edges. The bias strip can be made from purchased bias binding or cut from a matching or contrasting fabric.

SINGLE BIAS-BOUND HEM



DOUBLE BIAS-BOUND HEM




Interfaced hems

LEVEL OF DIFFICULTY **


On tailored garments, such as jackets and winter skirts, an interfaced hem can be used. It is only suitable for straight hems as it produces a heavy, structured edge. A sew-in woven interfacing cut on the bias grain is used for this technique.

- 1 Cut a bias strip of sew-in woven interfacing 2 in (5 cm) wide. If it requires joining, use a lapped seam.



- 2 Press up a 1½ in (4 cm) hem on the garment to the wrong side to make a hemline crease.

- 3 Place the interfacing to the crease line of the hem. Herringbone stitch the interfacing in place, stitching along the upper and lower edges.



- 4 Pin the hem up over the interfacing. A strip of interfacing should show at the upper edge of the hem.

- 5 Roll back the top edge of the hem. Herringbone stitch just to the interfacing.




- 6 Roll back the hem into position. Press. On the right side, no stitching will be visible.

Horsehair braid hems

LEVEL OF DIFFICULTY ***


On special-occasion wear, a horsehair braid is used in the hem edge as it will hold the edge out and give a look of fullness. Although once made from horsehair, the braid is now made from nylon. It is available in various widths. The braid is stretchy, so try not to stretch it when applying.

USING A NARROW HORSEHAIR BRAID



- 1 Place one edge of the braid to the edge of the hem, wrong side to wrong side.


- 2 Using a narrow zigzag, stitch along the other edge of the braid to secure.



- 3 Fold the braid on to the wrong side of the fabric along the zigzag stitching. Press into position.

- 4 Machine stitch with a straight stitch, through the center of the hem and braid. A row of machining will show on the right side.


USING A WIDE HORSEHAIR BRAID



- 1 Overlay by ¾ in (1 cm) the edge of the braid to the wrong side of the fabric. One side of the braid has white stitching on it; use the non-stitched edge. Pin in place.

- 2 Zigzag stitch in place, ¾ in (5 mm) from the edge of the braid.

- 3 On the right side, trim the fabric down to the zigzag stitching.



- 4 Press the hem and braid up on to the wrong side of the fabric.





- 5 Use a herringbone stitch to secure. If the hem is curved, pull up the white stitching at the edge of the braid to tighten the braid into shape.

Hems with banding

LEVEL OF DIFFICULTY ***

Banding is a term applied to a much wider bias strip. Some banding is visible by the same amount at the hem or edge on both sides of the work, while other bandings are surface-mounted to the edge of a fabric, such as for a decorative effect on a blind or a table runner. Dealing with the corners on banding needs accurate marking and stitching. Most of the following techniques are used primarily on craft and home furnishing items.

BANDING AT INNER CORNERS




BANDING AT OUTER CORNERS

1 Cut a bias banding strip $2\frac{1}{4}$ in (7 cm) wide. Press under the long edges to the wrong side by $\frac{3}{8}$ in (1 cm). Press the binding in half lengthwise, wrong side to wrong side.




2 Place the banding to the fabric, right side to right side. You can pin it in place if you like. Stitch along the crease line, stopping the machining $\frac{3}{8}$ in (1 cm) from the corner.



3 Fold the banding on to itself diagonally, wrong side to wrong side.

4 Using a pin or tailor's tack, mark on the banding the center foldline to the stitching. Then mark the same distance from the stitching line (indicated by the dotted red lines). Mark this point with a vertical pin.



5 Fold the banding at right angles on to itself, right side to right side, aligning edge to edge with the fabric. Make sure the vertical pin is at the fold.

6 Machine along the lower crease in the banding. Extend the machining through the folded part of the banding as well.


7 Stitch in the point for the banding corner as indicated by the dotted red lines. Trim to remove surplus fabric around the point.

8 Open out the banding and press the seams toward the banding.

9 Fold the banding to the wrong side of the fabric along the center crease line and press.

10 Fold in the mitered corners on either side. Pin in place.





11 Finish on the wrong side with a flat fell stitch.







12 Turn to the right side and press.



SURFACE-MOUNTED BANDING AT OUTER CORNERS





SURFACE-MOUNTED BANDING AT INNER CORNERS



Applying a flat trim

LEVEL OF DIFFICULTY *

On some items a flat trim braid or ribbon is added for a decorative effect. This may be right on the hem or edge, or placed just above it. To achieve a neat finish, any corners should be mitered.








Piped edges

LEVEL OF DIFFICULTY ***

A piped edge can look very effective on a garment, especially if it is made in a contrasting color or fabric. Piping is also an excellent way of finishing special-occasion wear as well as soft furnishings. The piping may be single, double, or gathered.

SINGLE PIPING



DOUBLE PIPING

1 Different thicknesses of piping cord can be used for this. Make up single piping (see steps 1–3, opposite page).

2 Cut another bias strip, in a contrasting color if you like.

3 Join the bias strip to the single piping, stitching next to the piping.

4 Place a second piping cord to the wrong side of the contrast strip.

5 Wrap the contrast strip around the cord and stitch.

6 Attach to the edge of the work as for single piping (see steps 4–7, opposite page). On the right side, there is a double row of piping at the edge.

GATHERED PIPING

1 This is a great technique to try on cushions. Cut a bias strip 2 in (5 cm) wide. Stitch the bias strip loosely around a piece of piping cord. Secure the cord to the bias at one end.

2 Push the bias along the cord to gather.

3 Machine the gathers in place. Secure the gathers at both ends of the cord.

Seam allowance

Gathered piping

4 Attach to the edge of the work as for single piping (see steps 4–7, opposite page).

Attaching a lace trim

LEVEL OF DIFFICULTY **

A lace edge can give a look of luxury to any garment. There are many ways of applying lace, depending on how the lace has been made. A heavy lace trim has a definite edge to be sewn on to the fabric. Lace edging has a decorative edge and an unfinished edge, whereas a galloon lace has decorative scallops on both edges.

HEAVY LACE TRIM

1 Pin the lace to the right side of the fabric.

2 Using a small zigzag stitch, machine along the edge of the lace. All of the stitching should be on the lace.

3 Trim away surplus fabric behind.

LACE EDGING

1 Place the lace to the fabric, right side to right side. Align the raw edges.

2 Machine using a straight stitch.

3 Turn the raw edges to the wrong side of the fabric. Press in place on to the wrong side.

4 Working from the right side of the fabric, zigzag stitch close to the fabric edge.

5 Trim away surplus fabric on the reverse side.

GALLOON LACE

1 Place the entire piece of lace to the right side of the fabric. Align the edge of the lace with the raw edge of the fabric. Pin in place.

2 Machine along the upper edge of the lace, following the shape.

3 Trim away surplus fabric following the shape of the stitching.


4 The lace trim on the right side.

Applying other trims

LEVEL OF DIFFICULTY ***

There are many kinds of trims—ribbons, braids, beads, feathers, sequins, fringes, and so on—that can be applied to a fabric edge. If a trim is made on a narrow ribbon or braid it can often be inserted into a seam during construction. Other trims are attached after the garment or item has been completed.


INSERTING A TRIM IN A SEAM



ATTACHING A TRIM TO AN EDGE



HAND STITCHING A TRIM








FASTENERS

There are many types of fastening available. Some of them are purely functional while others are more decorative as well as practical. A great many fastenings are hand stitched in place.


ZIPPERS

The zipper is probably the most used of all fastenings. There are a great many types available, in a variety of lengths, colors, and materials, but they all fall into one of five categories: skirt or pant zippers, metal or jeans zippers, invisible zippers, open-ended zippers, and decorative zippers.


Directory of zippers




CENTERED ZIPPER




CONCEALED OR
INVISIBLE ZIPPER




DECORATIVE ZIPPER



FLY-FRONT ZIPPER



LAPPED ZIPPER



OPEN-ENDED ZIPPER

How to shorten a zipper

LEVEL OF DIFFICULTY *

SHORTENING A SKIRT/PANT OR INVISIBLE ZIPPER

1 Using a zigzag stitch, width 5.0 and length 0.5, machine across the teeth of the zipper.

2 Cut off the surplus zipper below the stitching.

Zippers do not always come in the length that you need, but it is easy to shorten them. Skirt or pant zippers and invisible zippers are all shortened by stitching across the teeth or coils, whereas an open-ended zipper is shortened at the top and not at the bottom.

SHORTENING AN OPEN-ENDED ZIPPER

1 Mark with a marker the place where the zipper is to be shortened.

2 Open the zipper past this point.

3 Using a zigzag stitch, width 3.0 and length 0.5, machine across each side of the opened zipper. Cut off the surplus.

Marking for placing zippers

LEVEL OF DIFFICULTY *

For a zipper to sit accurately in the seam, the seam allowances where the zipper will be inserted need to be marked. The upper seam allowance at the top of the zipper also needs marking to ensure that the zipper pull sits just fractionally below the stitching line.

1 Stitch the seam, leaving a gap for the zipper.

2 Secure the end of the stitching.

3 Place a row of tacks along the stitching line through the opening.

4 Place a row of tacks along the upper seam allowance.

Lapped zipper

LEVEL OF DIFFICULTY **

A skirt zipper in a skirt or a dress is usually put in by means of a lapped zipper technique or a centered zipper technique (see opposite page). For both of these techniques, you will require the zipper foot on the sewing machine. A lapped zipper features one side of the seam—the left-hand side—covering the teeth of the zipper to conceal them.

1 Stitch the seam, leaving enough of the seam open to accommodate the zipper.

2 Secure the end of the stitching.

3 Insert the right-hand side of the zipper first. Fold back the right-hand seam allowance by $\frac{1}{2}$ in (1.3 cm) and press. This folded edge is not in line with the seam.

4 Place the folded edge against the zipper teeth. Baste.

5 Using the zipper foot, stitch along the baste line to secure the zipper tape to the fabric. Stitch from the bottom of the zipper to the top.

6 Fold back the left-hand seam allowance by $\frac{3}{8}$ in (1.5 cm) and press. Place the folded edge over the machine line of the other side. Pin and then hand-baste along foldline.

7 Starting at the bottom of the zipper, stitch across from the center seamline and then up the side of the zipper. The finished zipper should have the teeth covered by the fabric.

Centered zipper

LEVEL OF DIFFICULTY **

With a centered zipper, the two folded edges of the seam allowances meet over the center of the teeth, to conceal the zipper completely.

1 Stitch the seam, leaving a gap for the zipper.

2 Baste the rest of the seam allowance.

3 Press the seam open lightly.

4 Center the zipper behind the tacked part of the seam. Pin and then baste in place along both sides.

5 On the wrong side, lift the seam allowance and the zipper tape away from the main fabric. Pin.

6 Machine the zipper tape to the seam allowance. Make sure both sides of the zipper tape are secured to the seam allowances. Stitch through to the end of the zipper tape.

7 Working from the right side of the work, stitch down one side, across the bottom, and up the other side of the zipper.

8 Remove the tacks and press.

9 The finished zipper from the right side.

Faced fly-front zipper

LEVEL OF DIFFICULTY ***

Whether it be for a classic pair of pants or a pair of jeans, a fly front is the most common technique for inserting a pant zipper. The zipper usually has a facing behind it to prevent the zipper teeth from catching.

1 Stitch the seam, leaving a gap for the zipper.

2 Using tailor's tacks, mark the center front lines.

3 Trace baste the foldlines.

4 Trim the left-hand front of the opening straight, to measure $\frac{3}{8}$ in (1.5 cm) from the center line.

5 Neaten the edges on both sides.

6 Fold the left-hand front along the foldline and press.

7 Place the fold adjacent to the zipper teeth and pin in place. The zipper may be too long and will extend beyond the top of the fabric.

8 Machine along the foldline using the zipper foot. Extend the machining past the seam stitching line.

9 Fold the right front along the foldline. Place the foldline over the zipper and pin the foldline to the machine stitching on the left-hand side.

10 On the inside, pin the zipper tape to the fabric extension.

11 Machine the zipper tape to the fabric along the center of the tape.

12 On the right side, top-stitch around the zipper. Start stitching at the center front. Stitch a smooth curve.

13 Neaten all the edges of the fly-front facing, leaving the top edge raw.

14 On the wrong side, pin the facing to the left-hand side seam allowance. Ensure that the facing covers the zipper fully.

15 Machine to the seam allowance on the left-hand side.

16 Attach the waistband over the zipper and the facings. Trim the facing and zipper.

17 Secure the lower edge of the facing on the right-hand side to the right-hand seam allowance.

18 The waistband goes over the zipper and acts as the zipper stop. Attach a pant hook and eye.

Invisible zipper

LEVEL OF DIFFICULTY **

This type of zipper looks different from other zippers because the teeth are on the reverse and nothing except the pull is seen on the front. The zipper is inserted before the seam is stitched.

A special invisible zipper foot is required.

- 1** Mark the seam allowance with basting stitches.



- 2** Place the center of the zipper over the baste line, right side of zipper to right side of fabric. Pin in place.


- 3** Undo the zipper. Using the invisible zipper foot, stitch from the top of the zipper down. Stitch along the length of the zipper on the top and be careful not to stitch too close to the teeth. The machine will stop when the foot hits the zipper pull.



- 4** Do the zipper up. Place the other piece of fabric to the zipper. Match along the upper edge. Pin the other side of the zipper tape in place.



- 5** Open the zipper again. Using invisible zipper foot, stitch down the other side of the zipper to attach to the second piece of fabric. Remove any basting stitches.



- 6** Close the zipper. On the wrong side at the bottom of the zipper, the two rows of stitching that hold in the zipper should be finishing at the same place.



- 7** Stitch the seam below the zipper. Use the normal machine foot for this. There will be a gap of about 1/8 in (3 mm) between the stitching line for the zipper and that for the seam.



- 8** Stitch the last 1 1/4 in (3 cm) of the zipper tape to just the seam allowances. This will stop the zipper from pulling loose.









- 9** On the right side, the zipper is completely invisible, with just the pull visible at the top. Apply a waistband or facing and press.

Open-ended zipper

LEVEL OF DIFFICULTY **

The open-ended zipper is used on garments where the two halves need to be fully opened in order to put the garment on—for example, on a jacket or cardigan.




A decorative zipper

LEVEL OF DIFFICULTY ***


Some zippers are meant to be seen—they may have crystals in the teeth, or they may have decorative, colored teeth.

1 Place a piece of silk organza to the right side of the work, positioning it where the zipper will be.




2 Mark a rectangle on the organza the length and width of the zipper.

3 Stitch around the rectangle.



4 Slash centrally down between the stitching lines.

5 Slash into the corners.





6 Pull the organza through to the wrong side and press.

7 Place the zipper behind the opening. Pin in place along one side.

8 Pin in place along the other side.

9 Using the zipper foot, stitch in place. Stitch sharp corners.




10 On the right side, the zipper is exposed.


BUTTONS

Buttons are one of the oldest forms of fastening. They come in many shapes and sizes, and can be made from a variety of materials including shell, bone, plastic, nylon, and metal. Buttons are sewn to the fabric either through holes on their face, or through a hole in a stalk called a shank, which is on the back. Buttons are normally sewn on by hand, although a two-hole button can be sewn on by machine.


Directory of buttons




TWO-HOLE BUTTON




FOUR-HOLE BUTTON




COVERED BUTTON



NOVELTY BUTTON



RIVET BUTTON



SHANKED BUTTON

Sewing on a 2-hole button

LEVEL OF DIFFICULTY **

This is the most popular type of button and requires a thread shank to be made when sewing in place. A toothpick will help you to sew on this type of button.

1 Position the button on the fabric. Start with a double stitch and double thread in the needle.



2 Place the toothpick on top of the button. Stitch up and down through the holes, going over the stick.

3 Remove the toothpick.



4 Wrap the thread around the thread loops under the button to make a shank.

5 Take the thread through to the back of the fabric.



6 Buttonhole stitch over the loop of threads on the back of the work.

Sewing on a 4-hole button

LEVEL OF DIFFICULTY **

This is stitched in the same way as for a two-hole button except that the threads make an X over the button on the front.

1 Position the button on the fabric. Place a toothpick on the button.

2 Using double thread, stitch up and down through alternate sets of holes, over the toothpick. Make an X shape as you stitch.



3 Remove the toothpick.

4 Wrap the thread around the thread loops under the button to make the shank.



5 On the reverse of the fabric, buttonhole stitch over the thread loops in an X shape.



Sewing on a shanked button

LEVEL OF DIFFICULTY **

When sewing this type of button in place, use a toothpick under the button to enable you to make a thread shank on the underside of the fabric.

- 1 Position the button on the fabric. Hold a toothpick on the other side of the fabric, behind the button.



- 2 Using double thread, stitch the button to the fabric, through the shank.



- 3 Be sure each stitch goes through the fabric and around the toothpick beneath.




- 4 Remove the toothpick. Work buttonhole stitching over the looped thread shank.

Sewing on a reinforced button

LEVEL OF DIFFICULTY ***

A large, heavy button often features a second button sewn to it on the wrong side and stitched on with the same threads that secure the larger button. The smaller button helps support the weight of the larger button.



- 1 Position the large button on the right side of the fabric. Hold a smaller button beneath the fabric, in line with the large button.

- 2 Sew on the large button, stitching through to secure both buttons together.

- 3 When the stitching is complete, wrap the thread around the thread loops beneath the larger button. Secure with a double stitch.




Oversized and layered buttons

LEVEL OF DIFFICULTY **

There are some huge buttons available, many of which are really more decorative than functional. By layering buttons of varying sizes together, you can make an unusual feature on a garment or item of soft furnishing.

- 1 First position the oversized button on the fabric.

- 2 Top with a smaller button and stitch the two together to the fabric.






- 3 Place a small one-hole button on the layered buttons and attach to the thread using a buttonhole stitch.

Covered buttons

LEVEL OF DIFFICULTY **


Covered buttons are often found on expensive clothes and will add a professional finish to any jacket or other garment you make. A purchased buttonmaking gadget will enable you to create covered buttons very easily.




BUTTONHOLES

A buttonhole is essential if a button is to be truly functional, although for many oversized buttons, a snap fastener on the reverse is a better option, because the buttonhole would be just too big and could cause the garment to stretch.


Directory of buttonholes and button loops




BASIC BUTTONHOLE




ROUND-END BUTTONHOLE



KEYHOLE BUTTONHOLE



BOUND BUTTONHOLE



FROG FASTENER WITH
CHINESE BALL BUTTON






ROULEAU LOOPS



SPACED ROULEAU LOOPS

Stages of a buttonhole



A sewing machine stitches a buttonhole in three stages. The stitch can be slightly varied in width and length to suit the garment or craft item, but it needs to be tight and close together.



Positioning buttonholes

LEVEL OF DIFFICULTY *


Whether the buttonholes are to be stitched by machine or another type of buttonhole is to be made, the size of the button will need to be established in order to work out the position of the button on the fabric.



Vertical or horizontal?

As a general rule, buttonholes are only vertical on a garment when there is a placket or a strip into which the buttonhole fits. All other buttonholes should be horizontal. Any strain on the buttonhole will then pull to the end stop and prevent the button from coming undone.

HORIZONTAL BUTTONHOLES



VERTICAL BUTTONHOLES



Machine-made buttonholes

LEVEL OF DIFFICULTY *

Modern sewing machines can stitch various types of buttonhole, suitable for all kinds of garments. On many machines the button fits into a special foot, and a sensor on the machine determines the correct size of buttonhole. The width and length of the stitch can be altered to suit the fabric. Once the buttonhole has been stitched, always slash through with a buttonhole chisel, to ensure that the cut is clean.

BASIC BUTTONHOLE

The most popular shape for a buttonhole is square on both ends.



ROUND-END BUTTONHOLE

A buttonhole featuring one rounded end and one square end is used on lightweight jackets.



KEYHOLE BUTTONHOLE

This is also called a tailor's buttonhole. It has a square end and a keyhole end, and is used on jackets and coats.



Machine-corded buttonhole

LEVEL OF DIFFICULTY **

This buttonhole has a cord of heavier sewing thread running through it. You may have to consult your sewing machine manual for the positioning of the cord. This buttonhole is used for a bold buttonhole on a plain fabric.



1 Place the cord into the buttonhole foot as directed by your machine manual.

2 Work the buttonhole on the machine—the machine will stitch the buttonhole over the cord.



3 Gently pull on the ends of the cord to eliminate the loop.

4 Using a chenille size 18, thread the ends of the cord into a large needle.








5 Take the cord to the back of the fabric. Secure by hand with a back or whip stitch.

Piped buttonhole

LEVEL OF DIFFICULTY ***







A buttonhole can also be made using piping cord. This is a type of buttonhole that is worked early in the construction of the garment. Size 1 piping cord needs to be used, otherwise the buttonhole will be too bulky.





Patch method bound buttonhole

LEVEL OF DIFFICULTY ***

Another method of creating a buttonhole is to use a patch of fabric stitched on to the main fabric. The technique is ideal for jackets and coats. A contrast fabric can be used for an attractive detail. This is known as a bound buttonhole.









In-seam buttonhole

LEVEL OF DIFFICULTY *

This is a buttonhole formed in a seam allowance. It is found down decorative center fronts that feature seam detailing. It is a very discreet buttonhole.



BUTTON LOOPS

A buttonhole is not the only way of using buttons. Buttons can also be fastened by means of a fabric loop, which is usually attached at the edge of a garment. Fabric loops are often found on the back of special-occasion wear, where multiple loops secure rows of small, often covered buttons. Loops, called frog fasteners, can also be made from decorative cord.

Rouleau loop


LEVEL OF DIFFICULTY ***

This button loop is formed from a bias strip. Choose a smooth fabric for the strip as it will be easier to turn through. A rouleau loop is used with a round ball-type button.

- 1** Cut a bias strip $1\frac{1}{2}$ in (4 cm) wide. Fold lengthwise, right side to right side, and pin together.



- 2** Stitch with a seam allowance of $\frac{5}{8}$ in (1.5 cm) along the strip, keeping the edge of the machine foot against the folded edge.



- 3** Stitch another row $\frac{1}{16}$ in (2 mm) away from the first stitching. This is for strength.

- 4** Trim the bias close to the stitching.

- 6** Pin the prepared loop strip to the ironing board and press with a steam iron.



- 5** Turn the bias strip to the right side, using a loop turner.



Corded loop

LEVEL OF DIFFICULTY ***

It is possible to make a very fine button loop that has a cord running through it. This type of loop is suitable for lightweight fabrics. Use a shanked button with a corded loop.

- 1** Cut a bias strip $1\frac{1}{2}$ in (4 cm) wide, and any length. Cut a piece of cord twice the length of the strip.

- 2** Wrap the cord in the bias strip, folded wrong side to wrong side. Pin. Make sure the bias strip is near to one end of the cord.




- 3** Stitch along the bias strip, next to, but not too close to, the cord.

- 4** Machine another row $\frac{1}{16}$ in (2 mm) away from the first stitching.

- 5** Trim away the bias strip close to the stitching.


- 6** Stitch through the cord and bias strip in the center of the cord and near the end of the bias strip.



- 7** At the center point, ease the fabric over the cord to turn it to the right side.



- 8** Trim off the exposed ends of cord from the fabric loop.




Spacing the loops


LEVEL OF DIFFICULTY **

Once the loops have been made, the next step is to attach them to the garment. It is important that all the loops are the same size and positioned the same distance apart. To achieve this you will need to baste your fabric to mark the placement lines. The loops go on the right-hand front or the left-hand back of the work.


1 Mark the placement lines on the fabric using basting stitches. Be sure the horizontal lines are equally spaced.



2 Pin the loops to the fabric. The folded end of the loop should be on the inner basting line and the cut ends to the raw edge. Center the loop over the baste line.




3 Machine the loops just inside the seam allowance at the center line.



5 Place the facing or lining over the loops to finish.

4 Stitch another row to ensure the loops are secure.



6 The completed loop will extend from the edge of the fabric.

Frog fastenings

LEVEL OF DIFFICULTY ***

A loop made from a decorative cord is often found on garments with an Asian influence. These so-called frog fastenings can be purchased, although they are straightforward to make. A matching ball button can be made from cord as well, by twisting the cord over and under itself.

MAKING A FROG FASTENER



1 Using a fabric glue to secure the cord, twist the cord into the shape seen in the photograph and stick it on to the edge of the fabric. Hide the ends under the center.

2 Secure the cord by stitching along each edge with a small hand stitch. Use a matching thread.



TYING A BALL BUTTON



1 Start by making a loop in the cord.



2 Twist the cord to make another loop over the first loop. The end of the cord goes under the first side.



3 Take the cord over, under, over, and under all the other loops.




4 Pull the two ends to tighten into a ball button.

5 Stitch the ends into a decorative pattern to match the frog fastener.



OTHER FASTENINGS

There are many alternative ways to fasten garments, craft projects, and other items, some of which can be used instead of or in conjunction with other fasteners. These include hooks and eyes, snaps, tape fasteners, and laced eyelets.



Directory of other fastenings




HOOK AND LOOPED EYE




SKIRT/PANT HOOK AND EYE



SNAP FASTENER



SNAP TAPE




VELCRO™

Hooks and eyes


LEVEL OF DIFFICULTY **

There are a multitude of different types of hook and eye fasteners. Purchased hooks and eyes are made from metal and are normally silver or black in color. Different shaped hooks and eyes are used on different garments—large, broad hooks and eyes can be decorative and stitched to show on the outside, while the tiny fasteners are meant to be discreet. A hook that goes into a hand-worked eye produces a neat, close fastening.


ATTACHING HOOKS AND EYES



HAND-WORKED EYE



PANT HOOK AND EYE



Snaps

LEVEL OF DIFFICULTY **

A snap is a ball and socket fastener that is used to hold two overlapping edges closed. The ball side goes on top and the socket side underneath. Snaps can be round or square and can be made from metal or plastic.

1 Baste the ball and socket halves of the snap in place.



2 Secure permanently using a buttonhole stitch through each hole in the outer edge of the snap half.



3 Remove the bastes.



PLASTIC SNAPS

A plastic snap may be white or clear plastic and is usually square in shape. Stitch in place as for a metal snap (see left).



Tape fasteners

LEVEL OF DIFFICULTY **

In addition to individual small fasteners, there are fasteners in the form of tapes that can be sewn or stuck on. Velcro™, a hook and loop tape, is available in many colors and types. Sewn-on Velcro™ is ideal for both clothing and soft furnishings, while the stick-on variety can be used to fix curtain pelmets and blinds to battens on windows. Plain cotton tape with snap fasteners is used primarily in soft furnishings. Hook and eye tape is found in underwear or down the front of a shirt or jacket, where it can be very decorative.

VELCRO™

1 Pin the Velcro™ in place. The loop side should be underneath and the hook side on top.



2 Stitch around all the edges.



SNAP TAPE



1 Pin the tape in position.
Make sure the snaps align.



2 Use the zipper foot to stitch around all sides of the tape.

HOOK AND EYE TAPE



1 The eye side of the tape features a slot into which the fabric is inserted. Pin in place.

2 Stitch along the edge using either a stretch stitch or a narrow 3-step zigzag stitch.



3 Wrap the hook side of the tape over the raw edge of the fabric. Pin in place.


4 Stitch to match up with the eye side.

Eyelets

LEVEL OF DIFFICULTY **

An eyelet fastening can be very decorative and is often found on bridal wear and prom dresses. A piece of boning needs to be inserted into the fabric between the edge and the eyelets, to give strength. You will require eyelet pliers to punch the holes and then insert the eyelets.

1 Using the pliers, punch out the holes for the eyelets at 1¼–1½ in (3–4 cm) intervals.







2 Place an eyelet in each hole. Change the heads on the pliers and squeeze the eyelet in place.

3 Insert a row of eyelets on either side of the back opening.



4 To close, lace ribbon across from eyelet to eyelet and finish with a bow.





LININGS AND INTERFACINGS

Linings and interfacings are very important in sewing. Interfacings provide shape and structure in a garment or in soft furnishing, while a lining will make any garment more comfortable to wear as well as hiding the inside seams and stitching from view.

INTERLININGS AND INTERFACINGS

Interlinings are similar to interfacings, the difference being that an interfacing is an extra layer of fabric attached in a small area, while an interlining is attached to a whole garment or item. Interlinings and interfacings may be woven, knitted, or non-woven and can be applied with heat (fusible) or sewn-in. Always try to buy products recommended for domestic use. Be sure to cut all these fabrics on the straight of the grain even if they are non-woven.

Interlinings

These are fabrics that cover the inside of an entire garment. They are cut to the same pattern pieces and joined to the main fabric by means of basting stitches around the edges. The two layers are treated as one during construction.

MUSLIN



This is a cotton muslin. Use with wools and cottons, for jackets, skirts, and dresses.

SILK ORGANZA



An interlining of silk organza will give shape and structure. Use on special-occasion wear and silk fabrics as well as wool in tailored skirts.

DRESS NET



Net is used for bounce and rustle. Use in all special-occasion wear for effect and to prevent creasing.

Interfacings

LEVEL OF DIFFICULTY **

An interfacing may be fusible or non-fusible (sew-in) and is only attached to part of a garment or item. Sections of a garment normally interfaced include the collar and cuffs and the facings. In addition to fusible interfacings, there are also fusible tapes available, which are used to prevent a fabric from stretching and will support edges, and fusible webs that provide stiffening.


NON-FUSIBLE INTERFACINGS

All of these interfacings need to be basted to the main fabric around the edges prior to construction of the work or seam neatening.

Muslin

Silk organza

Non-woven interfacing




Alpaca tailoring canvas


Sometimes the interfacing does not cover the whole pattern piece, which occurs in tailored garments. Baste to the main fabric along the outer edges and herringbone stitch the inner edges.

FUSIBLE INTERFACINGS

A fusible interfacing is used in the same areas as a sew-in interfacing. To prevent the fusible interfacing from showing on the right side of the work, use pinking shears on the edge of the interfacing.



Lightweight woven fusible interfacing



Knitted fusible interfacing



Non-woven fusible interfacing

INTERFACINGS AND INTERLININGS COMBINED



Muslin interlining

Alpaca interfacing

On structured garments, there may be both interlining and interfacing. The interlining is applied first and the interfacing is attached on top. Baste around the outside edge and herringbone stitch the inner edges.

FRAME FUSING



Sew-in interfacing, seams removed

Fusible interfacing

This is a technique that combines a sew-in interfacing with a fusible. It is used in more structured garments to create tailored collars and cuffs. The fusible interfacing is placed on top to seal the sew-in interfacing in place in the seam allowances.

Seam allowance

STRAIGHT FUSIBLE TAPE



Straight grain tape is about $\frac{3}{4}$ in (2 cm) wide and has little give in it. Use it to stabilize edges. On some seams it may replace stay stitching. To fuse around curves, snip through the tape at 90 degrees.

BIAS FUSIBLE TAPE



Bias tape has a machined straight stitch through it. As the tape is cut on the bias, it will bend around curves. When fusing the tape in position, the stitching line in the tape should be on the fabric stitching line.

SLOTTED FUSIBLE TAPE




Slotted fusible is wider than other fusible tapes, and has a slotted edge. The tape is used to shape pocket tops and hems on jackets. Fuse in position so that the slots correspond to the foldline in the fabric.

Interfacings, facings, and linings

LEVEL OF DIFFICULTY **


On tailored and more structured garments, the facing will be interfaced and this is then attached to the lining.



1 Apply the interfacing to the facing.

2 Pin the interfaced facing to the lining.

Lining



3 Stitch together.

4 Press the seam toward the lining.



LININGS

A lining is placed inside a garment primarily to make the garment more comfortable to wear—it will prevent the garment from sticking to you. It will also make the garment last longer. Choose a good-quality lining made from rayon or acetate as these fabrics will breathe with your body. Polyester linings can be sticky to wear.

Lining a skirt

LEVEL OF DIFFICULTY ***


Cut the lining out the same as the skirt, using the same pattern pieces, and join together, leaving a gap for the zipper. Do not stitch in the darts.



Hemming a lining

LEVEL OF DIFFICULTY **



The lining on a skirt or dress should be slightly shorter—about 1½ in (4 cm)—than the finished garment, so that the lining does not show when you are walking or sitting.



Lining around a split

LEVEL OF DIFFICULTY ***



If there is a split in a hemline, the lining will need to be stitched around it securely. First construct the skirt, with its split finished, corners mitered, and hemmed. Finish the lining hem in the same way.



Lining a bodice

LEVEL OF DIFFICULTY ***

On dresses and fitted tops, a lined bodice is so comfortable and it reduces bulk. The insertion of a lining is done prior to the center back seam being joined and the side seams being joined.







PROFESSIONAL TECHNIQUES

Once you have mastered the basics of sewing, it is time to try some more advanced techniques, such as those involved in modern tailoring or boning a bodice for special-occasion wear. None of these techniques is difficult, but they take a little more time and care to execute.

SPEED TAILORING

Speed tailoring is the term given to modern tailoring techniques that use fusible interfacings to give shape and structure to a jacket or coat. Choose woven fusible interfacings and cut on the same grain as the jacket fabric pieces. If possible, use two different interfacings—one a medium weight and one a light weight—in conjunction with fusible tapes to stabilize the edges of the jacket. If interfacings of different weights are not available, choose a lightweight product and use two layers if required in the front of the jacket.

Components of a jacket

LEVEL OF DIFFICULTY ***

These photographs show where to place the fusible interfacing on a jacket or coat. Your pattern may be cut differently to this—the front and back may be one piece, not two as shown here, and you may have a two-piece sleeve—but the same principle will apply, of a heavier interfacing at the front and a lighter one at the back, with reinforcement through the shoulder.

FRONT



SIDE FRONT



SIDE BACK



BACK



SLEEVE



FRONT FACING




UPPER COLLAR



FINISHED JACKET



UNDER COLLAR



Jetted pocket

LEVEL OF DIFFICULTY ****

This is a professional pocket found on many suit jackets. Great care has to be taken when making this pocket because there is no flap for it to hide behind!

1 Cut out the welts (the strips that make the edges of the pocket). Apply lightweight fusible interfacing to them on the wrong side.



2 Transfer the marks from the pattern using tailor's tacks.

3 Press in half, wrong side to wrong side.



4 Start with the upper welt. Place it to the right side of the jacket front. The raw edge of the welt is toward the hem. Match the tailor's tacks. Pin in place.



5 Machine along the center of the welt. Stitch between the tailor's tacks only.

6 Position the lower welt on the jacket, placing the raw edge of the welt together.

7 Stitch through the center of the lower welt. Ensure both rows of stitching are exactly the same length.



8 Place the lining over the welts, raw edges to the center. Pin to secure.

9 Stitch the lining in place over the stitching line of the welts—you can feel the indentation of welt stitching.

10 Slash through the jacket fabric between the welts (see Jetted pocket with flap, pages 220–221).





11 Push the lining and the ends of the welts through to the back.

12 Press the lining and welts on the wrong side as shown.

Wrong side



Right side

Square ends on welts

13 On the right side, whip stitch the folds of the welts together.



14 On the reverse, stitch around the lining to make the pocket bag. The stitching starts and ends on the ends of the welts (see Jetted pocket with flap, pages 220–221).



15 Remove the whip stitches from across the pocket opening.



Collar application

LEVEL OF DIFFICULTY ****

A notched collar is a sign of a tailored jacket. This type of collar consists of an upper and under collar, and a facing that folds back to form the rever on either side. Careful stitching and accurate marking are required.

1 Attach the upper collar to the front facing and back neck lining.

2 Stop stitching at the tailor's tack at the front edge.

3 Press the seam open over a tailor's ham.

4 Clip the seam as necessary.

5 Join the under collar to the jacket front and back.

6 Stop stitching at the tailor's tack at the front edge.

7 Press the seam open. Clip as necessary.

8 Place the jacket and the lining together. Match the collar sections.

9 Stitch around the collar, stopping and starting the stitching at the tailor's tacks at the front edge.

10 Stitch the front facing to the jacket front. Start stitching at the tailor's tack at the front edge. The stitching line from the collar and the stitching line from the facing should line up but not cross each other.

11 Layer the seam.

12 On the inside, herringbone stitch the neck seams together.

13 Turn the collar and rever to the right side.

14 Press using a steam iron and cloth. Roll the seam toward the back of the garment so that it does not show on the right side.

Set-in sleeve

LEVEL OF DIFFICULTY ***

On a tailored jacket, the sleeve needs to be set in to have a rounded sleeve head, which is created with polyester batting. The sleeve head will ensure that the sleeve hangs perfectly.

1 Make up the sleeve.



2 Cut a piece of polyester batting to fit the sleeve head. The batting should be approx 2 in (5 cm) deep at the centre. Pin in place.



3 Insert two rows of gather (ease) stitches to attach the batting to the sleeve.

4 Insert the sleeve into the armhole, right side to right side. Pin in place.




5 Pull up the ease stitches to fit. The sleeve head will absorb the fullness.

6 Machine in place. Make a second row of machining close to the first stitching.



7 The shoulder pad can now be inserted. The back slope of the shoulder pad is longer than the front slope. The concave side will face the jacket lining.



8 Attach the shoulder pad at the edge of the sleeve seam using a firm running stitch.

9 On the right side, the finished sleeve has a rounded sleeve head.



Hem and lining

LEVEL OF DIFFICULTY ***

When making a jacket, the jacket hem is turned up first and then the lining is hemmed. The jacket hem needs to be reinforced first with a slotted fusible hem tape. Make sure that the hem edge is parallel to the ground.



1 Turn up the hem on the jacket by about 1 1/2 in (4 cm). Pin to secure.

2 Roll back the edge of the hem and herringbone stitch in place.

3 Bring the lining down over the jacket hem. Turn up the hem of the lining so that it is level to the jacket hem, then push up to 3/4 in (2 cm) from the hem edge. At the facing edge, the lining is level with the hem edge. Pin.



4 Use a slip hem stitch to secure the lining in place.

BONED BODICES




A strapless bodice will require boning inserted to prevent the bodice from falling down. The boning will also give extra structure to the bodice and prevent wrinkles. Boning can be a simple process, or more complex using interfacings for additional structure and shape.



Couture boned bodice

LEVEL OF DIFFICULTY ****

A couture boned bodice is the more complicated of the two methods of bodice construction, but it is well worth the extra work involved as the finished result is wrinkle-free and self-supporting. This technique can be used for bridal bodices and special-occasion wear.

COMPONENTS OF THE BODICE







A basic boning technique

LEVEL OF DIFFICULTY ***

For a simpler bodice on a dress or as a bodice on its own, this is a lightweight, quick technique.



APPLIQUÉ AND QUILTING

Simple finishing touches can be used to good effect on many items. The term appliqué applies to one fabric being stitched to another in a decorative manner. The fabric to be appliquéd must be interfaced to support the fabric that is to be attached. Appliqué can be drawn by hand, then cut and stitched down, or it can be created by a computer pattern on the embroidery machine. The embroidery machine can also be used to create quilting, or this can be done by hand or with a sewing machine.

Hand-drawn appliqué

LEVEL OF DIFFICULTY ***

This technique involves drawing the chosen design on to a piece of double-sided fusible web, after which the design is fused in place on fabric prior to being stitched.

1 Draw a decorative shape, such as a flower, on to a piece of double-sided fusible web.

2 Using the iron, fuse the web on to your chosen fabric.

3 Cut out the shape from the fabric.

4 Place the shape, fusible web side down, where it is to be positioned on fabric and fuse in place.

5 Using a wide, close zigzag stitch, stitch around the shape.

6 For a flower, stitch on top of the zigzag stitch, stitch fabric appliqué to make petal shapes.

Machine appliqué

LEVEL OF DIFFICULTY **

There are designs available for appliqué if you have an embroidery machine. You will need to use a special fusible embroidery backer on both the fabric for the appliqué and the base fabric.

1 Place the base fabric and appliqué fabric in the embroidery hoop and stitch out the first part of the design.

2 Trim the appliqué fabric back to the stitching lines.

3 Complete the computerized embroidery.

Quilting

LEVEL OF DIFFICULTY **

This is a technique that involves stitching through two layers of fabric, one of which is a batting. The stitching sinks into the batting, creating a padded effect. Quilting can be done by hand, with a sewing machine, or using computerized embroidery.

COMPONENTS OF QUILTING



HORIZONTAL QUILTING




Baste the batting and top fabric together. Stitch double lines with spaces between. Use a stitch length of 4.0 on your machine.

DIAMOND QUILTING

1 Diagonally baste the batting and top fabric together.



2 Set the machine to a stitch length of 4.0, with the needle on the one side of the foot. Stitch rows of machining diagonally across. Use the width of the machine foot as a guide to keep the rows parallel.




3 Stitch parallel rows in the opposite diagonal directions, to create diamond shapes.



FREEFORM QUILTING

Baste the batting and top fabric together. Stitch at random.



COMPUTERIZED QUILTING

Baste the batting and top fabric together, then stitch on a quilted pattern with the embroidery machine.







Roses and bows



LEVEL OF DIFFICULTY **

On special-occasion wear, a rose can add a superb finishing touch. When the raw edges of a rose are exposed, as in version 2 below, it also looks great made in tweed and suiting fabrics, to add a decorative finish to a tailored jacket. A bow that is permanently fixed in place is a beautiful embellishment on bridal wear.

ROSE VERSION 1



ROSE VERSION 2



BOW

1 To make the loops, cut a piece of silk or other fabric that is four times the length of the loop required and twice the width plus seam allowances.



2 Interline with dress net to the wrong side. Baste the net around the raw edge.



3 Fold in half, right side to right side. Stitch along the raw edge leaving a $\frac{3}{8}$ in (1.5 cm) seam allowance.

4 Turn through to the right side. Fold so that the seamline is in the center.



5 Bring the short end to the centre. Pin in place.

6 Baste through the center, using double thread.

7 Pull along the basting stitches to gather the center.



8 Next make the two ends. Cut two pieces of fabric the required finished length and twice the required width plus seam allowances.

9 Baste dress net to the fabric.



10 Fold each piece of fabric in half, right side to right side, and stitch along the long raw edge and at an angle at one end.

11 Remove bulk from the corners.



12 Turn through to the right side. Press. Make sure there are sharp points.

13 To assemble the bow, wrap a piece of fabric around the gathered center of the loops and stitch in place by hand.

14 Scrunch the raw ends of the ends together and hand stitch behind the loop.




INTERLINING CURTAINS






A lined curtain that is also interlined will not only hang beautifully but will also be warm and keep out any drafts. This technique is for hand-sewn curtains and requires a large, flat table to work on. There are different weights of interlining available.



Lined and interlined curtains

LEVEL OF DIFFICULTY ***

Preparation and accurate measuring of the window and the curtain fabric will ensure that this technique works every time. Choose a thicker quality curtain lining for interlined curtains because it will hang better.







A vertical needle is positioned to the left of the title 'MENDING'.

MENDING

Mending can preserve the life of your favorite clothes or furnishings. As a golden rule, always try to fix lost buttons or dropped hems as soon as possible. Here you will find more complex mending techniques for repairing split seams, ripped-off buttons, tears, and broken zippers.

MENDING

Repairing a tear in fabric, patching a worn area, or fixing a zipper or a buttonhole can add extra life to a garment or an item of soft furnishing. Repairs like these may seem tedious, but they are very easy to do and well worthwhile. For some of the mending techniques shown here, a contrast color thread has been used so that the stitching can be seen clearly. However, when making a repair, be sure to use a matching thread.

Unpicking stitches

LEVEL OF DIFFICULTY **

All repairs involve unpicking stitches. This must be done carefully to avoid damaging the fabric because the fabric will have to be restitched. There are three ways you can unpick stitches.

SMALL SCISSORS



Pull the fabric apart and, using very small, sharply pointed scissors, snip through the stitches that have been exposed.

SEAM RIPPER

Slide a seam ripper carefully under a stitch and cut it. Cut through every fourth or fifth stitch, and the seam will unravel easily.



PIN AND SCISSORS

On difficult fabrics or on very small, tight stitches, slide a pin under the stitch first to lift it away from the fabric, then snip through with a pair of sharply pointed scissors.




Darning a hole

LEVEL OF DIFFICULTY **

If you accidentally catch a piece of jewelry in a sweater or other knitted garment, it may make a small hole. Or a moth could cause this. It is worth darning the hole, especially if the sweater was expensive or is a favorite. Holes can also occur in the heels of socks and these can be darned in the same way. Machines often have a darning stitch.


1 Even if the hole is small, the sweater will be unwearable.



2 Using wool yarn, work several rows of running stitches vertically around the hole.




3 Complete the repair by working horizontal rows of running stitches through the vertical stitches.




Repairing fabric under a button

LEVEL OF DIFFICULTY **


A button under strain can sometimes pull off a garment. If this happens, a hole will be made in the fabric, which needs fixing before a new button can be stitched on.



1 On the right side of the fabric, the hole where the button has pulled off is clearly visible.



2 Turn to the wrong side and apply a patch of fusible interfacing over the hole.



3 Work a machine straight stitch over the hole on the right side to strengthen the fabric.

4 Stitch the button back in place.


Repairing a damaged buttonhole

LEVEL OF DIFFICULTY **


A buttonhole can sometimes rip at the end, or the stitching on the buttonhole can come unraveled. When repairing, use a thread that matches the fabric so the repair will be invisible.



1 On the right side of the fabric, the edges of the buttonhole stitching have torn and come unraveled.



2 Stitch over the torn sections by hand using a buttonhole stitch.





3 Reinforce the ends using small whip-stitches, close together.

Mending a split in a seam

LEVEL OF DIFFICULTY **

A split seam can be very quickly remedied with the help of some fusible mending tape and new stitching.




Mending a tear with a fusible



LEVEL OF DIFFICULTY *

Tears easily happen to clothing, especially children's wear, and they may occur on soft furnishings too. There are several methods for mending a tear. Most use a fusible patch of some kind, which may or may not be seen on the front, but you can also use a patch cut from matching fabric (see page 302).



FUSIBLE APPLIQUÉ PATCH







VISIBLE FUSED PATCH



3 Fuse the fabric in place on the right side.



FUSED PATCH ON THE WRONG SIDE



Mending a tear with a matching patch

LEVEL OF DIFFICULTY **

On a patterned fabric, such as a checker or a stripe, it is possible to mend a tear almost invisibly by using a patch that matches the pattern.

1 Cut a square hole in the fabric, removing the damaged area.

2 Turn under the raw edges of the hole by $\frac{3}{8}$ in (5 mm) and press.

3 Cut a piece of fabric from matching fabric to fill the hole (this fabric could be taken from the hem). Match the stripes or checks. Baste in place.

4 Using a small flat fell stitch, stitch the patch into the hole, working from the right side of the fabric.

5 This is how it will look on the reverse.

6 Remove the bastes and press.

Repairing or replacing elastic

LEVEL OF DIFFICULTY *

Elastic can frequently come unstitched inside the waistband, or it may lose its stretch and require replacing. Here is the simple way to re-insert elastic or insert new elastic.

1 Carefully unpick a seam in the elastic casing.

Old elastic



2 Pull the old elastic through the gap in the seam and cut through it.



3 Attach new elastic to the old with a safety pin. Use the old elastic to pull the new elastic through inside the casing.

4 Secure the ends on the new elastic.

5 Hand stitch the unpicked seam back together using a flat fell stitch.



Repairing a broken zipper

LEVEL OF DIFFICULTY **

Zippers can break if they come under too much strain. Sometimes the zipper has to be removed and a new zipper inserted. However, if only a few teeth have been broken far enough down so that the zipper can still be opened sufficiently, you can make this repair.

1 Where there are broken teeth on the zipper, the zipper pull will be attached to one half only. Move the puller up so it is alongside the gap in the teeth on the other side.


Broken teeth



Broken part of zipper

2 Carefully feed the teeth on the broken side into the top of the zipper.

3 Just above the broken part, hand stitch over the zipper teeth using double thread. This makes a stop for the puller and the zipper will now have an extended life.



PROJECTS

DRAWSTRING BAG

This pretty drawstring bag is suitable for evening wear and special occasions, especially for a bride or flower girl. Try using silk or satin for this—I have used two slightly different colors as the fabrics will provide lots of contrasting shadows. However, it would look very different if made in a floral cotton. The size of the bag can easily be adjusted by cutting the initial pattern larger or smaller. The ribbon drawstrings make looped handles for carrying the bag.


TECHNIQUES INVOLVED



PATTERN MARKING See page 82.



HOW TO APPLY A FUSIBLE INTERFACING
See page 54.



BUTTONHOLES See pages 263–264.



LEVEL OF DIFFICULTY *****

SHOPPING LIST

1¾ yd x 24 in (1.5 m x 60 cm)

non-woven fusible interfacing

30 x 45 in (75 x 115 cm) silk

dupion

30 x 45 in (75 x 115 cm) contrast

silk

1 spool thread

Beads, to decorate

2¼ yd (2 m) ribbon, ½–⅝ in (12–15 mm) wide

1 Draw around a large plate on to a 30 in (75 cm) piece of pattern paper. Mark bold lines that can be traced.


2 Draw two more circles around this circle, the first one 1 in (2.5 cm) larger and the second one 2 in (5 cm) larger.

3 Find the center of the circle by folding the paper, and then divide the circle into 16 segments.

4 Extend these lines 4 in (10 cm) beyond the pattern.

5 Join the ends of alternate lines to the circle to make points.


6 This is your pattern. Cut out carefully.



7 Cut the interfacing in half. Take one piece of interfacing and place it over the paper pattern. Using a soft pencil or water-soluble marker, trace the pattern on to the interfacing.


8 Apply a piece of interfacing to the wrong side of each piece of silk—the interfacing with the pattern marked on it is fused to what will be the outer layer of silk.

9 Pin the two pieces of silk together, right side to right side. Cut out, following the pattern lines marked on the interfacing.






10 Trace baste the two inner circles on the pattern. Cut through the thread loops.

11 Carefully separate the two pieces of silk, snipping through the trace bastings.



12 On the interfaced side of the outer layer of silk, mark the position of the two buttonholes. They should be on opposite sides of the bag, between the trace-basted lines.








22 Insert a piece of ribbon into one of the buttonholes, using a safety pin to thread it through the channel. Exit by the same buttonhole and tie the ends together to make a loop.

23 Repeat with another piece of ribbon and the other buttonhole, so that one piece of ribbon is threaded clockwise and one counterclockwise.

24 Pull on the ribbon loops to close the bag. If you like, tie ribbon around the outside and finish with a bow.



BOOK COVER

Matching stationery can make office work far more enjoyable, so why not try covering a notebook or diary? A cover will make the book easy to find, as well as protecting the corners. It looks great in a vibrant silk dupion but works just as well with other fabrics, such as cotton. For a finishing touch, decorate the cover with beads or ribbon.

TECHNIQUES INVOLVED



HOW TO APPLY A FUSIBLE INTERFACING
See page 54.



QUILTING See page 291.



LEVEL OF DIFFICULTY ***

SHOPPING LIST

For a notebook:

16 x 46 in (40 x 115 cm) silk dupion or cotton fabric

16 x 36 in (40 x 90 cm) heavy fusible interfacing

16 x 36 in (40 x 90 cm) polyester

batting ($\frac{1}{4}$ in (6 mm) thickness)

16 x 46 in (40 x 115 cm) tear-away







embroidery stabilizer

1 spool machine embroidery thread


16 x 46 in (40 x 115 cm) contrast lining

16 x 46 in (40 x 115 cm) double-sided fusible web


Beads, to decorate

**1** Apply a fusible interfacing on to the wrong side of the fabric.**2** Cut out fabric and lining according to the cutting diagram. Cut batting and tear-away embroidery stabilizer to fit piece 1.**3** Place the batting under piece 1, and tear-away embroidery stabilizer under the batting. Pin all together to secure.**4** Using tailor's chalk, divide this piece into three sections by drawing a $1\frac{1}{2}$ in (4 cm) wide strip vertically down the center. Machine a row of decorative stitches down the strip.**5** Draw diagonal lines on one of the larger sections.**6** Stitch along the chalk lines using a decorative stitch.**7** Draw lines in the opposite direction and machine decorative stitches.


8 On the other large section, stitch lines at random.



9 Stitch a second line alongside.



11 Using a fusible web, fuse the lining to this quilted section.



10 Repeat in the opposite direction.




12 Using a fusible web, fuse the lining to pieces 2 and 3, the flaps.



13 Zigzag stitch one long edge of each flap. Use a stitch width of 3.0 and a stitch length of 1.0.



14 Place the raw edge of each flap to the edge of the book cover, wrong side to wrong side. Zigzag stitch together.



15 Zigzag all around the book cover sides, stitching over the flap as you do so. Stitch again to reinforce the edges.



16 If you wish, decorate with beads to finish. Take a small double stitch, thread on a bead, and make another stitch.



CUSHION

A unique cushion can add a luxurious look to any sofa or bed. This one features a gathered frill and a decorative gathered panel. It is in a plain silk fabric so that the sheen shows off the gathers, but you could try a tartan or stripe for a different look. Make half a dozen of these in coordinating colors for a very rich effect.

TECHNIQUES INVOLVED



HOW TO MAKE GATHERS See page 127



DOUBLE RUFFLE VERSION 3 See page 137.



INVISIBLE ZIPPER See page 255.



LEVEL OF DIFFICULTY ****


SHOPPING LIST

1½ x 1½ yd (145 x 115 cm) silk

1 x 16 in (40 cm) concealed zipper

1 spool polyester all-purpose thread

1 cushion pad, 16 x 16 in (40 x 40 cm)



1 Take piece 1. Work two rows of gather stitches along each side.



2 Pull up the gathers until the strip measures 16½ in (42 cm) long.

3 Place the gathered strip in between pieces 2 and 3.



4 Join right side to right side, and stitch the strip between the rectangles, using a ½ in (1.5 cm) seam allowance. Press the seam to the non gathered side. Make sure the piece measures 16½ x 16½ in (42 x 42 cm). Trim if necessary.





5 On the right side, the central gathered strip meets the side panels neatly.

6 Make a double ruffle. Cut out pieces 4–7 and join together, right side to right side, to make a very long strip. Press the seams open. Fold the strip in half lengthwise wrong side to wrong side. Divide into four equal sections and mark with pins. Place two rows of gather stitches between each set of pins.



7 Start to gently pull up the gathers.



CHILD'S SKIRT

This is a simple skirt, cut from a long strip of fabric. The skirt features tucks at the hem edge that have been top stitched to produce a decorative effect, and then embroidered with a machine stitch. The waist edge of the skirt has an elasticated finish. This pattern could be adapted for a child of any age—or even an adult.

TECHNIQUES INVOLVED



PLAIN TUCKS See page 111.



MAKING A CASING AT THE WAIST EDGE
See page 172.



HAND-STITCHED HEMS: SERGING FINISH
See page 230.



LEVEL OF DIFFICULTY ****

SHOPPING LIST


For a child age six:

22 x 46 in (55 x 115 cm) cotton
fabric

1 spool matching thread


Contrast embroidery thread

1 x 20 in (2.5 x 50 cm) non-roll
elastic




1 Fold the fabric in half, right side to right side, and stitch down the 22 in (55 cm) side seam. Press and neaten.

2 Mark the hemline, and serge or zigzag the raw edge. Turn up the hem using a blind hem stitch.



3 Turn the skirt to the right side. Mark five horizontal tuck lines around the lower edge of the skirt at 2 in (5cm) intervals. Fold the tuck lines and press with the iron, then machine in place.

4 Divide the skirt vertically into 12 equal sections. Mark these with pins.




5 At the pinned points, alternately push the tucks up or down, and machine to secure. This creates a twist in the tuck.

6 On all of the tucks pointing toward the waist, stitch over the machining with a decorative stitch, or do this by hand.



7 At the top of the decorative stitching, hand stitch a flower using straight stitches: one stitch; a second stitch across it at right angles; a third stitch at an angle; and finally a fourth stitch at right angles to the third.



8 To make a casing, fold down the waist edge of the skirt twice.

9 Top-stitch along the top folded edge.

10 Stitch along the lower edge of the casing, leaving a gap for inserting the elastic.

11 Insert the elastic into the casing and machine the ends together. Hand stitch across the gap.



APRON

An apron is a simple project, and makes an ideal present. It could coordinate with your kitchen or may be worn for work in the yard. You could try making the apron in a print or stripe fabric, using a heavy cotton material that will wash. As not much fabric is required, you should look in the remnant bin at your local store.

TECHNIQUES INVOLVED



3-THREAD SERGER STITCH See page 93.



HOW TO CUT BIAS STRIPS See page 147





KANGAROO POCKETS See page 225.



LEVEL OF DIFFICULTY **

SHOPPING LIST

1½ x 1¾ yd (1 x 1.5 m) fabric
 24 x 46 in (60 x 115 cm)
 contrast fabric
 1 spool matching thread for
 each fabric



1 Serge or zigzag the three sides of the apron skirt (piece 1).




2 Turn under the edges, using a single hem, by ¾ in (2 cm).

3 Machine to secure.



4 From piece 3, cut bias strips 20 x 1½ in (50 x 4 cm). Apply to the two armhole seams, wrong side of bias to right side of armhole, turning under the edges of the strips.



5 From piece 3, cut bias strips 20 x 3 in (50 x 8 cm). Pin to top edge of apron.



6 Machine all bias strips in place. Wrap to the wrong side, turn under the raw edge, and machine to secure.

7 Cut the pocket (piece 2) from the contrast fabric.


8 Mark the center line with a row of basting stitches.



9 Neaten all the pocket edges with serger or zigzag stitching.

10 Turn under the curved edge by $\frac{3}{8}$ in (5 mm) and machine in place.

11 Turn under all the straight edges by $\frac{3}{8}$ in (1.5 cm). Pin, then press.



12 Place the pocket to the apron front approximately 13 in (32 cm) from the top edge. Machine along the straight edges.

13 Machine two rows of stitching down the center of the pocket.



14 Machine to reinforce the corners.

15 To make the tie ends, cut strips measuring approximately 36 x $2\frac{3}{4}$ in (90 x 7 cm). Press under the long sides by $\frac{3}{8}$ in (1 cm).

16 Press the strips lengthwise in half. Top-stitch both edges to complete.



17 Cut another strip of fabric 24 x $2\frac{3}{4}$ in (60 x 7 cm) and make the neck tie in the same way.



18 Attach the side tie ends and the neck tie to the apron.

19 Stitch an X in the square at each corner for strength.

SEWING AIDS

Here's a perfect starting point if you are new to sewing—make yourself some matching sewing aids: a scissor cover, needle case, and pin cushion. This project allows you to practice your machine stitching and experiment with a range of decorative stitches. Cotton fabric and machine embroidery thread works well, but you could always try silk fabric or variegated embroidery thread.

TECHNIQUES INVOLVED



DECORATIVE STITCHES See page 93.


HOW TO MAKE A PLAIN SEAM See page 94.



LEVEL OF DIFFICULTY **

SHOPPING LIST

12 x 46 in (30 x 115 cm) cotton fabric
 12 x 46 in (30 x 115 cm) heavy fusible interfacing
 1 spool machine embroidery thread
 12 x 35 in (30 x 90 cm) polyester batting
 2 3/8 yd (2 m) very narrow ribbon
 2 6 x 5 in (15 x 12 cm) squares felt
 Approx. 3 oz (85 g) amount polyester stuffing



1 Cut the piece of fabric in half through the fold. The top layer is to be embroidered and the under layer is the lining. Before cutting out the individual pieces, apply a heavyweight fusible interfacing to the top fabric layer.

2 Choose four or five decorative stitches and stitch vertical rows on the top layer. Use the width of the machine foot as a guide.

3 Now cut out the embroidered fabric and the lining according to the cutting diagram.



Scissor holder



1 Place the batting behind the embroidered piece 1.



2 Place the lining piece 1 over the embroidered fabric, right side to right side.

3 Stitch all around the edge, leaving a gap of about 4 in (10 cm) for turning.

4 Trim the seams to reduce bulk. Press, then turn the fabric through to the right side while still warm. Hand stitch the gap.

5 Fold one side of the square down. Make sure that your scissors fit into this folded section. Edge-stitch to secure and press.



6 Fold the other side across the first side, to the folded edge.

7 Stitch two-thirds of the way up, through all layers.



8 Fold down the corner of the upper layer and press.




9 Sew on a ribbon bow to trim the edge.



Needle case

1 Trim $\frac{3}{4}$ in (2 cm) off the short side of lining piece 3.



2 Stitch the short edges of the lining and embroidered piece 3 together, right side to right side. (The embroidered fabric will appear too big—just let it bulge out.) Stitch ribbon ties in to the middle of each side as you sew.




3 Fold the short ends of the embroidered fabric toward the lining so that the fabric lies flat.

4 Stitch along the long edge.



5 Turn through the other long edge. Hand stitch the lower edge with a blind hem or flat fell stitch.



6 Place the pieces of felt on the needle case and attach by stitching down the center.



7 Pin your needles to the felt to keep them safe and organized.

Pin cushion



1 Place lining piece 2 to the embroidered piece 2, right side to right side.



2 Stitch around all four sides, curving off the corners. Leave a small gap of 2¼ in (6 cm) in the center of one side for turning.

3 Turn through to the right side and stuff with polyester stuffing. Hand stitch the gap. Trim with a bow to finish.

THE SHOPPING BAG

It's easy to make your own stylish bag. There are some amazing handles available to purchase in the stores, and you could replace the burlap used here with denim or heavy cotton. You can make the bag to your own measurements, if you would like it to be longer or deeper—just remember to use the template for the lower corners.

TECHNIQUES INVOLVED



STITCH FINISHES See page 103.



STRAIGHT DARTED TUCKS See page 113.



MACHINE-STITCHED BELT CARRIERS
See page 181.




LEVEL OF DIFFICULTY ***

SHOPPING LIST

1 x 1½ yd (1 m x 115 cm) burlap
1 spool thread

1 pair bag handles
1.1 x 1½ yd (1 m x 115 cm) cotton
fabric for lining



1 Mark the tucks and corners on to piece 1 with chalk. Pin the tucks in place.

2 Attach the band (piece 2) to the top edge of piece 1 over the tucks using a ½ in (1.5 cm) seam allowance.



3 Press the seam open and top stitch.

4 Join the side seams from the top, stopping at the dot. Press the seam open.




5 Fold the corners by bringing the slash lines together.



6 Stitch along the diagonal lines. Press the corners up. Turn to the right side.

7 To make the four carrier strips, fold the long edges of pieces 3 and 4 to the center, then fold the strip lengthwise in half.

8 Machine down the folded edge through all layers to join the halves.



9 Wrap the carriers around the handles and pin in place.



10 Turn down the top edge of the bag by 2 in (5 cm) and pin. Place the handles to this top edge. Make sure they are in the center by measuring the distance of the carriers from either end.

11 Secure in place with straight stitching.



12 Make up the lining to match the bag (steps 1-6).

13 Cut a piece of thick cardboard to fit the bottom of the bag. Insert the cardboard and then the lining (turning its top edge down by about 2 3/4 in/7 cm so it does not show at the top, wrong side to wrong side).




14 Hand stitch the lining in place using a flat fell stitch. If you wish, stitch the lining and bag together through the corners.

BABY TOWEL

A snuggly towel for a baby or toddler is a must-make project. If you cannot find terry cloth, you can always buy a large bath towel and cut it up. Choose a contrast or matching binding and terry cloth for the edges and the ears. You could even embroider on eyes, a mouth, and whiskers!

TECHNIQUES INVOLVED



HAND STITCHES See pages 90–91.





BIAS-BOUND HEMS See page 238.




LEVEL OF DIFFICULTY ***

SHOPPING LIST

1½ yd x 1¼ yd
(1.2 m x 1.5 m) terry
cloth, or one large
bath towel for the
wrap and a hand
towel for the hood
1 contrast color face
towel for the inside
of the ears
1 spool thread
5½ yd x ¾ in (5 m x
2 cm) bias binding
(same color as inside
of ears)



3 Make the ears.
Cut out two from the terry cloth and two from the face towel. Place one ear of each color together, right side to right side. Pin together.






DOOR ORGANIZER

Just what do you do with all the clutter in a bathroom, bedroom, or child's room? Keep it all in this stylish door organizer. Use a strong cotton fabric, such as curtain material, as it will not require interfacing, and choose colors that will complement your room. The coat hanger needs to be straight in order to hang the fabric effectively—some hangers slope too much.

TECHNIQUES INVOLVED



PLEATS ON THE RIGHT SIDE See page 115.



ATTACHING A TRIM TO AN EDGE See page 247.




LEVEL OF DIFFICULTY ****

SHOPPING LIST


1 x 1½ yd (1 m x 115 cm)
heavy cotton, linen,
drill, or damask fabric
20 x ¾ in (50 x 2 cm)
stretch ribbon

1 spool matching thread
1½ yd (1.2 m) decorative
flat trim
1 straight, padded coat
hanger



1 Place ribbon (without stretching it) on to the right side of piece 1, 4 in (10 cm) from the top edge. Secure at the ends with machining.

2 Stitch vertically across the ribbon. This creates sections for small objects, such as pens or brushes.



3 Take piece 4 and press lengthwise in half, wrong side to wrong side. Apply trim along the pressed edge.




4 Mark with clips the position of the pleats. Fold the fabric to make pleats. Press.

5 Place the raw edge of piece 4 to the lower edge of piece 1 and pin in place. This will make the lower pocket.



6 Stitch the pocket band at either end to secure, then stitch vertically in the middle of the pleat.



7 Fold and trim piece 3 in the same way as steps 3 and 4 to make the upper pocket. Make and press the pleat.


8 On piece 1, use a row of bastes to mark the placement line for the upper pocket 11 in (27 cm) from the top edge.



9 Pin the raw edge of the upper pocket, right side to right side, along this placement line. Machine stitch in place.

10 Trim away any bulk. Turn the pocket up into position and carefully press.

11 Stitch either end to secure, and then vertically between the pleat.




12 On piece 2 draw the shape of the coat hanger on to the wrong side of the fabric, using tailor's chalk.



13 Pin pieces 1 and 2 together, right side to right side.

14 Following the shape of the coat hanger, stitch around. Use a $\frac{3}{8}$ in (1 cm) seam allowance, and leave a gap at the bottom edge and center top for the coat hanger. Both gaps should be about $\frac{1}{2}$ in (1 cm). Clip the seams, press seam allowances open and flat, and then turn.

15 Insert the coat hanger. To finish, hand stitch, using a blind hem stitch, to close the gap.



ROMAN BLIND

A Roman blind is a great way to provide privacy at a window and a splash of color in the room. The blind is quick and straightforward to make and will easily fit behind curtains if you so desire. Careful measuring of the window is essential, and a trip to the hardware store will be required to purchase the doweling and the slat for the bottom edge. You will need a batten fixed to the top of the window frame from which to hang the blind.

TECHNIQUES INVOLVED



MACHINED CURTAIN HEMS See page 234



TAPE FASTENERS See page 272.



LEVEL OF DIFFICULTY *****

SHOPPING LIST

Fabric: to calculate the amount you need, measure the window's width (at the widest part where the blind will hang), and also the drop (the finished length of the blind). Add 5 in (12 cm) to the width and 6 in (15 cm) to the drop for the hems—2 in (5 cm) at the top and 4 in (10 cm) at the bottom

Curtain lining, of matching size

1 spool matching thread

Decorative trim (optional)

Sew-and-stick Velcro™

2 or more pieces of wooden doweling to fit

1½ in (4 cm) x finished width slat of wood

Plastic curtain rings, about ¾ in (1 cm) diameter

Blind cord

1 Press under 2½ in (6 cm) down either side of the blind fabric (single fold hem).

2 Press up a double hem on the bottom edge to give a finished depth of 2 in (5 cm). Press in a mitered corner.

3 Trim the lining at the side edges by 1½ in (4 cm) each side. Press under a side hem of 2½ in (6 cm).

4 Place the lining to the blind fabric, wrong side to wrong side, so that the cut edge of the lining sits along the hem crease of the fabric. The folded side hems should be 1½ in (4 cm) from the folded edge of the blind. Pin in place.

5 Before securing the lining, make the casings for the wooden doweling. Measure the lining, and form a pleat at regular intervals. The pleats need to be at regular 12–16 in (30–40 cm) intervals, starting 16 in (40 cm) from the hem.

6 Re-position the lining to the blind. Machine across the pleat through both blind and lining to secure. Make sure you leave an opening wide enough to fit the doweling through.

7 Using a flat fell stitch, hand stitch the lining to the blind down the sides. Leave the ends of the pleats open.

8 Machine the bottom hem in place, over the lining. Leave the ends open.




9 Place a row of stitching at the lower edge of the hem to keep the hem fold sharp.

10 If you wish to add trim, you will need a length equal to the finished width of the blind plus 2 in (5 cm) for turnings. Machine it in place using a zipper foot over either of these rows of stitching.



11 Turn down the top edge so that the blind measures the required finished length. Pin in place.



12 Cut a piece of Velcro™ equal to the width of the blind. Sew the soft loop side of the Velcro™ to the blind along the top hem edge.

13 Insert wooden doweling through the pleats, and a slat through the hem. Hand stitch the ends closed with a flat fell stitch.



14 Using a buttonhole stitch, sew a curtain ring on to each end of the pleats, and at regular intervals along the doweling. One, two, or three rings may be required, depending on the width and weight of the blind. Make sure all the rings are in line with each other.



15 Add another row of rings just underneath the Velcro™.

16 For each set of rings, you need blind cord equal to twice the drop. Knot blind cord around each ring closest to the hem.




17 Thread the cord up through each line of rings (see illustration, right). Take all of the cords to one side at the top (see top right). Trim cords to level, and knot to secure.



18 To finish, stick the other side (the hook side) of the piece of Velcro™ to a batten on the window and attach the blind.

HOW TO THREAD A ROMAN BLIND



MAN'S TIE

This is not a difficult project, and it is great fun to make your partner a tie from the remnants of your favorite dress, especially if you are invited to a function that requires you to look stylish! Or you could try a tie in a fun cartoon print.

TECHNIQUES INVOLVED



HOW TO MAKE A PLAIN SEAM See page 94.



MACHINE STITCHES See pages 92–93.



HOW TO APPLY A NON-FUSIBLE INTERFACING
See page 55.



LEVEL OF DIFFICULTY ***

SHOPPING LIST


28 x 46 in (70 x 115 cm) fabric

28 x 46 in (70 x 115 cm) medium-weight

woven sew-in interfacing

1 spool matching thread

Remnant of lining, about 12 in (30 cm)



1 Cut pieces 1 and 2 from the tie fabric and interfacing on the bias, and pieces 3 and 4 from lining. Join the interfacing using a lapped seam and a zigzag stitch.



2 Join pieces 1 and 2 of the tie fabric together along the short edge using a plain seam, and press it open.



3 Baste the interfacing and fabric together, wrong side to wrong side.



PLACE MAT

Quilted place mats will be an asset to any table. Not only are they functional, they also protect the table from excessive heat. The mats feature a slot for a napkin and a pocket to hold your utensils. Use a pre-shrunk cotton fabric to make these as then they can be laundered regularly. Choose a toning color for the napkin and bound edges.


TECHNIQUES INVOLVED



SELF-LINED PATCH POCKET See page 214.



BIAS-BOUND HEMS See page 238.



QUILTING See page 291.



LEVEL OF DIFFICULTY **


SHOPPING LIST

For each place mat:

- 16 x 60 in (40 x 1.5 m) fabric to suit the room: cotton or linen are usually ideal
- 16 x 35 in (40 x 90 cm) polyester batting, (¼ in/6 mm thickness)
- 1 spool matching thread
- 60 x ¾ in (1.5 m x 2 cm) bias binding

For one napkin:

- 16 x 24 in (40 x 60 cm) cotton or polycotton fabric



1 Layer together piece 1, the batting, and the second piece 1 with the right side of the fabric to the outside. Use diagonal basting stitches to stop them from moving while quilting. As an alternative, you could use quilters safety pins.



2 Using a stitch length of 3.5, quilt the fabric. Start in the center to keep the fabric from moving and causing curved lines, and work to either side. Trim the edges to neaten, if necessary.


3 Fold the pocket (piece 2) in half to make a piece measuring 5 1/4 x 7 1/2 in (13 x 18 cm). Pin.



4 Machine down one of the 13 cm (5 in) sides. Turn to the right side and press.

5 Place the pocket flush to the right-hand corner of the quilt and pin in place.

6 Machine the seamed side of the pocket to the quilted mat.



7 Stitch vertical lines to make pockets for the cutlery. To help make lines straight, use a ruler to draw a stitch line with chalk.

8 Fold the napkin holder (piece 3) in half lengthwise and stitch. Turn and press the loop, then secure to the mat. Squeeze long edges together and down to fit under the machine foot.



9 Next bind the edges. Place the binding to the mat, right side binding to wrong side mat, aligning the raw edges. Machine together, turning under the edges as you begin.



10 Bring the binding to the right side and machine in place.



11 Make the napkin. For the serged effect, use a 3-thread serger stitch and an embroidery thread on the upper looper to stitch around all four sides, pivoting around the corners—this will keep one long seam. Thread the ends of the serger stitch back into the work. Press.

12 For the rolled hem effect, set the sewing machine to a zigzag stitch and use a rolled hem foot to stitch around the napkin.

KIMONO

A kimono-style dressing gown always looks stylish. You can use any fabric—this kimono is made from a heavy polyester satin, but a cotton would look pretty too. A shorter version could also be made. The obi sash holds the kimono tightly around the waist.


TECHNIQUES INVOLVED



KIMONO SLEEVE See page 194.



MACHINED HEMS See page 232.



OBİ SASH See pages 184–185.





LEVEL OF DIFFICULTY *****

SHOPPING LIST

2½ x 1⅓ yd (2.2 x 1.5 m) fabric for kimono, such as polyester satin,

cotton print, brocade, or “Chinese-type” satin brocade
30 in x 1⅓ yd (75 cm x 1.5 m)
contrast color fabric for obi sash

1 spool matching thread for each fabric
30 x 46 in (75 x 115 cm) very firm fusible interfacing



NOTE: This pattern is for 36 in/92 cm hip; 38 in/96 cm finished length

1 With a serger, overlock all the edges of the kimono pieces, except for the hems and front edges.




2 Join the back (piece 1) to the two front pieces (double piece 2) at the shoulder seams, using a $\frac{3}{8}$ in (1.5 cm) seam allowance. Press open.



3 Attach the two sleeves (double piece 3), from the center point on the sleeve to the shoulder seam. Machine at $\frac{3}{8}$ in (1.5 cm). Press open.

4 Join the side seams of the kimono, stopping at the sleeves. Join the sleeves.



5 Join piece 4 to piece 5 to make one long band and press the seam open. Press the band in half lengthwise, wrong side to wrong side.

6 Center the join in the band at the back of the neck. Pin to the kimono, right side to right side. Machine in place, stopping 8 in (20 cm) above the hem on each front edge.

7 Neaten the hem of the kimono (not the band) with a serger or zigzag stitch. Turn up by 1½ in (4 cm).



8 Use a blind hem stitch on the machine to secure.

9 Turn up the hem on the band to match the finished kimono hem. Top-stitch to hold in place.



10 With serger, overlock the band-to-kimono seam and press. Top-stitch to hold in place.



11 Turn up the hem on each sleeve once.

12 Machine in place.



To make the obi sash

1 Cut two strips of fabric 46 x 8 in (115 x 20 cm) for the tie ends. Fold in half lengthwise, right side to right side.

2 Stitch down the long side and at an angle on one end.

3 Press and turn the tie end to the right side. Press again, making sure the seam is on the edge.



4 Cut two pieces of fabric 12 x 8 in (30 x 20 cm) for the center section. Shape as required.

5 Apply a very heavy fusible interfacing to the wrong side of one piece. Curve off the edges of both pieces until the short ends measure 4 in (10 cm).

6 Center the tie ends to the short ends of the stiffened piece, on the right side. Machine to secure.



7 Place the other piece of fabric on top of the stiffened piece, right side to right side. Pin in place. Tuck the tie ends inside.

8 Machine all around, leaving a gap of about 6 in (15 cm) for turning in the center of one long edge. Ensure the tie ends are not caught in the stitching. Reduce the seam allowance using pinking shears.




9 Pull the tie ends through the gap. Turn the center section through to the right side and press. Hand stitch the gap with a blind hem stitch.

10 Tie the sash around the kimono to finish.

BABY BLANKET

This fleece baby blanket can be cut to any size—it could fit into a crib or even make a cosy wrap in the stroller. A soft washable wool or acrylic would also be ideal. The edges of the blanket have been bound with a soft satin polyester to make a contrasting tactile edge for the baby, but they could be bound in cotton if you prefer.

TECHNIQUES INVOLVED



EMBROIDERY See page 36.



HEMS WITH BANDING See pages 240–243.



APPLIQUÉ See page 290.



LEVEL OF DIFFICULTY ***

SHOPPING LIST

1 x 1½ yd (1 m x 1.5 m)

polar fleece

Fusible appliqué or machine embroidery threads



1 spool matching thread

12 in x 1½ yd (30 x 115 cm) satin

polyester (or cotton) for binding

1 Cut out two pieces of fleece large enough to fit the baby's cot. Adjust size according to whether the blanket will be tucked in, or just lie on top of the mattress. If you are going to machine embroider the fleece, this is the time to do so, following your machine's instruction manual.

2 Hand baste the two pieces of fleece together, wrong side to wrong side, around the outside edge. Make sure to do this on a flat surface to help avoid wrinkles.



3 To estimate the amount of bias binding you'll need, first measure around the edge of the blanket. Add on about 3½ in (9 cm) for each corner. Now cut bias strips 5 in (12 cm) wide from the satin and join them to make a strip that is long enough to go all around the blanket. Apply the binding to the edge of the blanket. Satin can be very slippery to handle, so beginners might want to use cotton for the binding instead.



4 As all four corners of the binding need to match, it is a good idea to make a triangular shaped template from construction paper to give the angle of the point. Machine one point first and make sure it is correct, then trace off the stitching lines to make your template.

5 Turn the binding to the right side and feel for bulky surplus fabric. Trim away.



6 Turn under the edge of the binding and flat fell stitch in place.



7 If you are using a fusible appliqué, apply the appliqué using the iron and a pressing cloth.

8 Fold up your completed teddy blanket ready to present to the lucky baby of your choice!



BOLSTER PILLOW

This is an easy project to make, even though it looks quite complicated. Make at least two of these—they look great on a bed or nestling along the sides of a sofa. Experiment with contrast piping and look in the stores for decorative tassels that can be sewn on to the ends. The instructions can be adapted to suit any size of bolster.

TECHNIQUES INVOLVED



HOW TO MAKE GATHERS See page 127.




PIPED EDGES See pages 244–245.




LEVEL OF DIFFICULTY ***

SHOPPING LIST

20 x 46 in (50 x 115 cm) fabric
 1¾ yd (1.5 m) piping cord
 1 spool matching thread
 1 bolster polyfill form, 17 x 7 in (42 x 17 cm)
 2 tassels



1 Make two bias strips, 1½ in (4 cm) wide and 24 in (60 cm) long, from piece 4.



2 Wrap each bias strip around a length of piping cord (see page 392) and pin in place.

3 Machine stitch using the zipper foot.




4 Stitch the piping to the two long ends of piece 1. Align all the raw edges, then pin and machine in place.

5 Place pieces 2 and 3 over the piping cord, one at either end, right side to right side. Pin in place.



6 Machine close to the piping using the zipper foot.



7 Turn under the unattached edges of pieces 2 and 3 to the wrong side by ½ in (1.5 cm). Press if required. Then, using a long stitch on your sewing machine, insert two rows of gather stitches.

8 Fold the cushion fabric in half lengthwise, right side to right side, matching the piping with the ends.



9 Machine a $\frac{3}{8}$ in (1.5 cm) seam and press the seam open.

10 Turn to the right side.



11 Pull the fabric over the bolster pad, so that the pad is between the piping.



12 To seal the raw ends, gently pull up the gather stitches to close. Using double top stitching thread, use a running stitch and pull the edges together. Now stitch the end closed.

13 To finish, sew a tassel on to each end.



JEWELRY ROLL

Going away? Where do you put your jewelry? This handy wrap will fit into any handbag or weekend holdall, and keep not only earrings but also your rings and chains. It could easily be adjusted to have more than one ring holder and could also have a larger zipper pocket or two.

TECHNIQUES INVOLVED



UNLINED PATCH POCKET See page 213.



PIPED EDGES See pages 244–245.




CENTERED ZIPPER See page 253.




LEVEL OF DIFFICULTY ***

SHOPPING LIST

24 x 46 in (60 x 115 cm)
silk dupion
24 x 46 in (60 x 115 cm)
non-woven fusible
interfacing
10 x 35 in (25 x 90 cm)
batting
7 in (18 cm) skirt zipper
1 spool matching thread
1 snap fastener
1 yd (1 m) no. 3 piping
cord
1 yd x $\frac{3}{16}$ in (1 m x 5 mm)
ribbon



1 Prior to cutting out, apply the fusible interfacing to the silk. Pin the batting securely to the top layer of piece 1 (the top of the jewelry roll) and baste across diagonally to secure.



2 Make a pocket with the zipper. Take piece 3 and press in half, wrong side to wrong side. Place the folded pressed edge to the side of the zipper and stitch in place with the zipper foot.




3 Place this piece of fabric on to the right-hand end of piece 2 (the base of the jewelry roll) and pin to secure.

4 Take piece 4 and press under $\frac{5}{8}$ in (1.5 cm) along one short edge. Place the pressed edge along the other side of the zipper, and pin in place.



5 Using the zipper foot, stitch along the side of the zipper through all layers. This makes a pocket on just the right-hand side.




6 To make a pocket at the other end, take piece 5 and press in half, wrong side to wrong side. Edge-stitch along the folded side.




8 To make the ring holder, take piece 6 and a piece of batting $2\frac{1}{2} \times 9$ in (6 x 22 cm). Wrap the silk around the batting to make a fat tube shape, turning in the raw edge on one end.



7 Place this piece to the left-hand side of the base and pin around the edges to secure. Stitch along the center of the piece to make two pockets.



9 Secure by hand with a flat fell stitch.




10 Pin the ring holder to the base of the jewelry roll between the pockets. Sew a snap close to the end of the ring holder.




11 Cut $1\frac{1}{2}$ in (4 cm) wide bias strips from piece 7 for the piping. With the cord, make up enough piping to go all around the edge of the roll.

12 Round off the corners of the base fabric and top fabric by drawing around a large thread spool.

13 Stitch the piping to the base.



14 Before attaching the top layer, stitch on the ribbon ties. Attach one piece of ribbon at the center point on the left-hand side and another piece about 6 in (15 cm) to the right of this piece.



15 Place the top piece to the base, right side to right side. Using the zipper foot, stitch the two sections together along the piping. Remember to leave a gap to turn through.

16 Trim and layer the seams. Turn through and press. Hand stitch the gap with a flat fell or blind hem stitch to finish.

POLAR FLEECE HAT & SCARF

This must be the easiest project ever! Suitable for both children and adults, this matching hat-and-scarf set keeps you so warm in the winter months. As polar fleece fabric is available in a wide variety of colors and prints, you can make yourself a whole wardrobe of hats and scarves. These also make perfect Christmas presents.

TECHNIQUES INVOLVED



MACHINE STITCHES See pages 92–93.



HOW TO MAKE A PLAIN SEAM See page 94.



HEMS See pages 231–232.



LEVEL OF DIFFICULTY *

SHOPPING LIST

1 x 1½ yd (90 cm x 1.5 m) polar fleece—this will make approximately two hats and one scarf

1 spool of matching thread

1½ yd (1 m) ribbon

Hat




1 Cut out a square of fleece, the measurement being the head circumference plus seams. Stitch together to make a tube.

2 Stop stitching 6 in (15 cm) from the end.



3 Baste around the top of the tube at this point.

4 Cut strips ¾ in (1 cm) wide down to the basting.



5 On the non-fringed end, turn up the hem to the wrong side—approximately 4 in (10 cm) on an adult hat and 3 in (8 cm) on a child's hat.

6 Zigzag stitch the hem in place.






7 Then turn up the hem to the right side.



8 Cut a strip of fleece ¾ in (1 cm) wide. Tie it tightly around the end of the fringing (over the basting stitches), to make a tassel.

9 Decorate the hem with a bow.

Scarf



CAFÉ CURTAIN

A café curtain is a half curtain that fits the lower part of a window for privacy but allows the light in at the top. A café curtain can be made from a curtaining fabric or you could use a semi-sheer voile. It hangs from a simple rod that fits across the window.

TECHNIQUES INVOLVED



ATTACHING A FACING See page 176.



HEMS ON CURTAINS See pages 234–235.



COVERED BUTTONS See page 261.



LEVEL OF DIFFICULTY ****

SHOPPING LIST

Fabric: to calculate the amount you need, measure the window's width, where the track for the curtain will be, and also the drop (the finished length of the curtain). Multiply the width measurement by 2.5 in order to give fullness (you may have to join fabric to obtain this width). Add 8 in (20 cm) on to the width and 16 in (40 cm) on to the drop for the hems. You'll also need 12 in (30 cm) for the facing and tabs

Materials to make large covered buttons (i.e. buttons and scraps of fabric)

1 spool matching thread

1 On all sides of the curtain fabric, press 2 in (5 cm) under to the wrong side once. Fold under 2 in (5 cm) again and press. Turn up the hem and machine in place close to the upper folded edge.



2 At the hem edge, press a double hem into position 4 in (10 cm) deep.

3 Unfold and miter the corner. Press into place again and machine.

4 Hand-stitch across the corner of the miter.



5 To make the tabs, cut straight grain strips 5¼ x 10 in (14 x 24 cm). Fold in half lengthwise, right side to right side, and machine.

6 Fold the fabric so that the seam is in the center of the strip, and press open.



7 Using a template, stitch one end of each tab into a point. Draw around the template with tailor's chalk to make sure all the tabs are the same.

8 Clip, turn through to the right side, and press.



9 Place the tabs to the upper edge of the curtain, seam-side down to the curtain and matching at the raw edge. Place a tab at each side and the rest at equal distances, approximately every 12 in (30 cm).

10 Pin the tabs into position.



11 For the facing, cut a strip of fabric 4 in (10 cm) wide and as long as the curtain width.

12 Place the facing over the tabs, right side to right side, and machine in place along the top edge.



13 Press the seam and turn the facing to the wrong side. Top-stitch.



14 Fold under the lower edge of the facing and machine in place.

15 Cover a large button for each tab. Fold the tab over the front of the curtain, to create a loop for the curtain rod. Sew a button on to each tab to secure it to the curtain.



DIRECTORY OF FASHION AND SOFT FURNISHINGS


Shirts




LADIES' SHIRT



MEN'S SHIRT




MEN'S FITTED SHIRT




LADIES' DRESS SHIRT




CHILDREN'S DRESS SHIRT



WING-COLLAR DRESS SHIRT



DENIM SHIRT



SHORT-SLEEVED SHIRT




WESTERN-STYLE SHIRT 1




WESTERN-STYLE SHIRT 2


Tops



T-SHIRT STYLE




SHELL



HALTER




STRETCH




DRAPED COWL



SMOCK



BUSTIER




ASYMMETRIC




LOOSE-FITTING


Blouses



TIE NECK



ROLL NECK




SLEEVELESS



WRAP




BLOUSE WITH YOKE



KAFTAN



GYPSY




VICTORIAN



CHINESE-STYLE


Cardigans, sweaters, and vests




ROUND-NECK CLASSIC
CARDIGAN




SCOOP-NECK CARDIGAN



TIE-FRONT




LONG
SWEATER-STYLE




CASUAL KNITTED JACKET




SHORT KIMONO-STYLE



POLO-NECK



KNITTED V-NECK



SLEEVELESS V-NECK


Skirts




STRAIGHT TAILORED




SKIRT WITH GODETS



BUTTON-THROUGH




GORED




CIRCULAR




PLEATED



KILT




PUFFBALL



GYPSY


Dresses




TAILORED




WRAP




EMPIRE




1960S-STYLE




SHIRT WAISTER




CHINESE-STYLE



COAT DRESS




HALTER NECK



BALLGOWN

Pants and shorts




CLASSIC PANTS




TAPERED PANTS




TIGHT JEANS




JODHPURS



COMBAT PANTS




DRAWSTRING PANTS



OXFORD BAGS



SHORTS



WALKING SHORTS

Jackets




CLASSIC-TAILORED



DOUBLE-BREASTED




TUXEDO



MILITARY-STYLE BLOUSON




BOLERO




OUTERWEAR JACKET



PARKA



BOMBER




SAFARI


Coats




CLASSIC



CLASSIC DOUBLE-BREASTED



TRENCH



FLY FRONT




NEHRU-STYLE



DUFFLE



PEACOCK




COCOON-STYLE




CAPE


Cushions




BOLSTER




ROUND




SQUARE BOX




FRILLED-EDGE




PIPED-EDGE




OXFORD-STYLE



CUSHION WITH TASSES




CUSHION WITH RIBBON TIES




BUTTON-TRIMMED


Blinds




ROMAN WITH
SOFT HEM




ROMAN WITH
SCALLOPED HEM




ROMAN WITH
SHAPED HEM




ROLL-UP




SIDE GATHERED




FAN



AUSTRIAN




DOUBLE STAGECOACH




PORTIER PANEL


Curtains




CAFÉ WITH TIE TOP



CAFÉ WITH TAB TOP




DRAPED




TAB-TOP SIDE
DRAPED




TIE TOP




GOBLET PLEAT



GOBLET PLEAT ON VALANCE



PENCIL PLEAT



PENCIL PLEAT WITH RUFFLE

GLOSSARY

Acetate Manmade fabric widely used for linings.

Acrylic Manmade fabric resembling wool.

Alpaca Canvas made from wool and alpaca. This fabric can be used as a non-fusible interfacing.

Appliqué One piece of fabric being stitched to another in a decorative manner.

Armhole Opening in a garment for the sleeve and arm.

Arrowhead Small, triangular set of straight stitches worked either by hand or by machine across a seam to add strength at a point of possible strain (for example, at the top of a split).

Back stitch A strong hand stitch with a double stitch on the wrong side, used for outlining and seaming.

Banding Method of finishing a raw edge by applying a wide strip of fabric over it. The strip can also be used to add length to a garment.

Bar baste A hand-worked bar of buttonhole stitches used to loosely attach two layers of fabric.

Basting stitch A temporary running stitch used to hold pieces of fabric together or for transferring pattern markings to fabric.

Belt carrier Loop made from a strip of fabric, which is used to support a belt at the waist edge of a garment.

Bias 45-degree line on fabric that falls between the lengthwise and the crosswise grain. Fabric cut on the bias drapes well. *See also* Grain.

Bias binding Narrow strips of fabric cut on the bias. Used to give a neat finish to hems and seam allowances.

Binding Method of finishing a raw edge by wrapping it in a strip of bias-cut fabric.

Blanket stitch Hand stitch worked along the raw or finished edge of fabric to neaten, and for decorative purposes.

Blind hem stitch Tiny hand stitch used to attach one piece of fabric to another, mainly to secure hems. Also a machine stitch consisting of two or three straight stitches and one wide zigzag stitch.

Blind tuck A tuck that is stitched so that it touches the adjacent tuck without machine stitches showing. *See also* Tuck.

Bobbin Round holder beneath the needle plate of a sewing machine on which the thread is wound.

Bodice Upper body section of a garment.

Bodkin Blunt-headed needle used for threading elastic or cord through a casing or heading.

Boning Narrow nylon, plastic, or metal strip, available in various widths, that is used for stiffening and shaping close-fitting garments, such as bodices.

Box pleat Pleat formed on the wrong side of the fabric, and fuller than a knife pleat. *See also* Pleat.

Broderie anglaise A fine plain-weave cotton embroidered to make small decorative holes.

Buttonhole Opening through which a button is inserted to form a fastening. Buttonholes are usually machine stitched but may also be worked by hand or piped for reinforcement or decorative effect.

Buttonhole chisel Very sharp, small chisel that cuts cleanly through a machine-stitched buttonhole.

Buttonhole stitch Hand stitch that wraps over the raw edges of a buttonhole to neaten and strengthen them. Machine-stitched buttonholes are worked with a close zigzag stitch.

Button shank Stem of a button that allows room for the buttonhole to fit under the button when joined.

Calico A plain weave, usually unbleached fabric.

Cashmere The most luxurious of all wools.

Casing Tunnel of fabric created by parallel rows of stitching, through which elastic or a drawstring cord is threaded. Often used at a waist edge. Sometimes extra fabric is required to make a casing; this can be applied to the inside or outside of the garment.

Catch stitch *See also* Slip hem stitch.

Challis Fine woollen fabric with uneven surface texture.

Chambray A light cotton with a colored warp thread.

Chiffon Strong, fine, transparent silk.

Chintz Floral print or plain cotton fabric with a glazed finish.

Clapper Wooden aid that is used to pound creases into heavy fabric after steaming.

Contour dart Also known as double-pointed dart, this is used to give shape at the waist of a garment. It is like two darts joined together. *See also* Dart.

Corded gathers Gathers that are pulled up over a narrow cord or thick thread, used for thicker fabrics. *See also* Gathers.

Corded seam A seam with piping in it, often used to join together two different fabrics.

Corded shirring A method of shirring where a piece of piping cord is stitched into a fold in the fabric. *See also* Shirring.

Corded tuck Substantial fold of fabric that has a cord running through it. *See also* Tuck.

Corduroy A soft pile fabric with distinctive stripes.

Cotton Soft, durable, and inexpensive fabric widely used in dressmaking. Made from the fibrous hairs covering the seed pods of the cotton plant.

Crease Line formed in fabric by pressing a fold.

Crepe Soft fabric made from twisted yarn.

Crepe de chine Medium-weight fabric with uneven surface, often made from silk.

Crinkle cotton Cotton fabric with creases added by a heat process.

Cross stitch A temporary hand stitch used to hold pleats in place and to secure linings. It can also be used for decoration.

Cross tuck Tuck that crosses over another by being stitched in opposite directions. *See also* Tuck.

Curtain weight Weight inserted into the bottom hem of a curtain to hold the curtain in place and make it hang properly.

Cutting line Solid line on a pattern piece used as a guide for cutting out fabric.

Cutting mat Self-healing mat used in conjunction with a rotary cutter to protect the blade and the cutting surface.

Damask Woven cotton with a floral pattern.

Darning Mending holes or worn areas in a knitted garment by weaving threads in rows along the grain of the fabric.

Dart Tapered stitched fold of fabric used on a garment to give it shape so that it can fit around the contours of the body. There are different types of dart, but all are used mainly on women's clothing.

Darted tuck A tuck that can be used to give fullness of fabric at the bust or hip. *See also* Tuck.

Denim Hard-wearing twill weave fabric with colored warp and white weft.

Double-pointed dart *See* Contour dart

Double ruffle Decorative trim made from two plain ruffles where one side is longer than the other. Also a ruffle made from doubled fabric.

Drape The way a fabric falls into graceful folds; drape varies with each fabric.

Dressmaker's carbon paper Used along with a tracing wheel to transfer pattern markings to fabric. Available in a variety of colors.

Drill Hard-wearing twill or plain-weave fabric with the same color warp and weft.

Drop The length of fabric required to make a curtain, the “drop” being the measurement from top to bottom of the window.

Duchesse satin Heavy, expensive satin fabric.

Dupion Fabric with a distinctive weft yarn with many nubby bits; made from 100 percent silk.

Ease Distributing fullness in fabric when joining two seams together of slightly different lengths, for example a sleeve to an armhole.

Ease stitch Long machine stitch, used to ease in fullness where the distance between notches is slightly greater on one seam edge than on the other.

Embroidery machine A machine that is capable of embellishing fabric with embroidery designs.

Enclosed edge Raw fabric edge that is concealed within a seam or binding.

Facing Layer of fabric placed on the inside of a garment and used to finish off raw edges of an armhole or neck of a garment. Usually a separate piece of fabric, the facing can sometimes be an extension of the garment itself.

Felt A natural wool fabric can felt when it is stimulated by friction and lubricated by moisture and the fibers bond together to form a cloth. Felting can also be done in a washing machine in a hot cycle.

Filament fibers Very fine synthetic thread, manufactured using plant materials and minerals.

Flannel Wool or cotton with a lightly brushed surface.

Flat fell seam See *Run and fell seam*.

Flat fell stitch A strong, secure stitch used to hold two layers together permanently. Often used to secure linings and bias bindings.

French dart Curved dart used on the front of a garment. See also *Dart*.

French seam A seam traditionally used on sheer and silk fabrics. It is stitched twice, first on the right side of the work and then on the wrong side, enclosing the first seam. See also *Mock French seam*.

Frog fastener Decorative fastener made from cord arranged into four overlapping loops stitched at the center. Used with a Chinese ball button.

Fusible tape Straight grain tape used to stabilize edges and also replace stay stitching. The heat of the iron fuses it into position.

Gabardine Hard-wearing fabric with a distinctive weave.

Galloon lace Decorative lace trim shaped on both sides, used to edge a hem.

Gathers Bunches of fabric created by sewing two parallel rows of loose stitching, then pulling the threads up so that the fabric gathers and reduces in size to fit the required space.

Georgette Soft, filmy silk fabric.

Gingham Two-color, plaid cotton fabric.

Goblet pleat Decorative curtain heading in which the fabric is stitched into narrow tubes that are then stuffed with batting. See also *Pleat*.

Godet A section that is inserted into a garment to give fullness at the hem edge. It is usually triangular in shape but it can also be a semi-circle. See also *Pleat*.

Grain Lengthwise and crosswise direction of threads in a fabric. Fabric grain affects how a fabric hangs and drapes.

Grosgrain Synthetic, ribbed fabric often used to make ribbons.

Gusset Small piece of fabric shaped to fit into a slash or seam for added ease of movement.

Haberdashery Term that covers all the bits and pieces needed to complete a pattern, such as fasteners, elastics, ribbons, and trims.

Habutai Smooth, fine silk originally from Japan.

Heading tape Wide fabric tape containing loops that is stitched to the top of a curtain. Hooks are inserted into the loops and then attached to a rail. The heading tape is drawn up to make pleats.

Hem The edge of a piece of fabric neatened and stitched to prevent unraveling. There are several methods of doing this, both by hand and by machine.

Hem allowance Amount of fabric allowed for turning under to make the hem.

Hemline Crease or foldline along which a hem is marked.

Hemming tape Fusible tape with adhesive on both sides. Iron in place to fuse and secure hems that are difficult to hand stitch.

Herringbone stitch Hand stitch used to secure hems and interlinings. Worked from left to right.

Herringbone weave A zigzag weave where the weft yarn goes under and over warp yarns in a staggered pattern.

Hong Kong finish A method of neatening raw edges particularly on wool and linen. Bias-cut strips are wrapped around the raw edge.

Hook and eye fastening Two-part metal fastening used to fasten overlapping edges of fabric where a neat join is required. Available in a wide variety of styles.

Horsehair braid A braid that is woven from strands of nylon thread and sewn into the hemlines of dressy garments to stiffen the lower edge.

Interfacing A fabric placed between garment and facing to give structure and support. Available in different thicknesses, interfacing can be fusible (bonds to the fabric by applying heat) or non-fusible (needs to be sewn to the fabric).

Interlining Layer of fabric attached to the main fabric prior to construction, to cover the inside of an entire garment to provide extra warmth or bulk. The two layers are then treated as one. Often used in jackets and coats.

Jacquard loom Device used in weaving to control individual yarns. This allows looms to produce intricately patterned fabric such as tapestry, brocade, and damask.

Jersey Cotton or wool yarn that has been knitted to give stretch.

Jettied pocket A type of pocket found on tailored jackets and coats. It consists of strips of fabric that form the edges of the pocket (welts) and the lining.

Keyhole buttonhole stitch A machine buttonhole stitch characterized by having one square end while the other end is shaped like a loop to accommodate the button's shank without distorting the fabric. Often used on jackets.

Kick pleat Inverted pleat extending upward from the hemline of a narrow skirt to allow freedom when walking. See also *Pleat*.

Knife pleat Pleat formed on the right side of the fabric where all the pleats face the same direction. See also *Pleat*.

Lapped seam Used on fabrics that do not fray, such as suede and leather, the seam allowance of one edge is placed over the edge to be joined, then top-stitched close to the overlapping edge. Also called an overlaid seam.

Lightening stitch See *Stretch stitch*.

Linen Natural fiber derived from the stem of the flax plant, linen is available in a variety of qualities and weights.

Lining Underlying fabric layer used to give a neat finish to an item, as well as concealing the stitching and seams of a garment.

Locking stitch A machine stitch where the upper and lower threads in the machine “lock” together at the start or end of a row of stitching.

Madras Brightly colored, unevenly checkered plaid cotton fabric from India.

Matka A silk suiting fabric with uneven yarn.

Miter The diagonal line made where two edges of a piece of fabric meet at a corner, produced by folding. See also **Mitered corner**.

Mitered corner Diagonal seam formed when fabric is joined at a corner. After stitching, excess fabric is cut away.

Mock casing Where there is an effect of a casing, but in fact elastic is attached to the waist, or is used only at the back in a partial casing.

Mock French seam Similar to a French seam, but best used on cotton or finer fine fabrics. It is constructed on the wrong side of the work. See also **French seam**.

Mohair Fluffy wool yarn cloth used for sweaters, jackets, and soft furnishings.

Multi-size pattern Paper pattern printed with cutting lines for a range of sizes on each pattern piece.

Muslin Fine, plain open-weave cotton.

Nap The raised pile on a fabric made during the weaving process, or a print pointing one way. When cutting out pattern pieces, make sure that the nap runs in the same direction.

Needle threader Gadget that pulls thread through the eye of a needle. Useful for needles with small eyes.

Notch V-shaped marking on a pattern piece used for aligning one piece with another. Also V-shaped cut taken to reduce seam bulk.

Notion An item of haberdashery, other than fabric, needed to complete a project, such as a button, zipper, or elastic. Notions are normally listed on the pattern envelope.

Nylon Hard-wearing, man-made fabric.

Organza Thin, sheer fabric made from silk or polyester.

Overedge stitch Machine stitch worked over the edge of a seam allowance and used for neatening the edges of fabric.

Overlaid seam See **Lapped seam**.

Over-stitch See **Buttonhole stitch**.

Pattern markings Symbols printed on a paper pattern to indicate the fabric grain, foldline, and construction details, such as darts, notches, and tucks. These should be transferred to the fabric using tailor's chalk or tailor's tacks.

Pencil pleat The most common curtain heading where the fabric forms a row of parallel vertical pleats. See also **Pleat**.

Petersham Stiff, ridged tape that is 1 in (2.5 cm) wide and curved. It can be used as an alternative finish to facing.

Pile Raised loops on the surface of a fabric, for example velvet.

Pill A small, fuzzy ball formed from tangled fibers which is formed on the surface of a fabric, making it look old and worn; it is often caused by friction. To remove fabric pills, stretch the fabric over a curved surface and carefully cut or shave off the pills.

Pinking A method of neatening raw edges of fray-resistant fabric using pinking shears. This will leave a zigzag edge.

Pinking shears Cutting tool with serrated blades, used to trim raw edges of fray-resistant fabrics to neaten seam edges.

Pin tuck Narrow, regularly spaced fold or gather. See also **Tuck**.

Piped tuck See **Corded tuck**.

Piping Trim made from bias-cut strips of fabric, usually containing a cord. Used to edge garments or soft furnishings.

Pivoting Technique used to machine stitch a corner. The machine is stopped at the corner with the needle in the fabric, then the foot is raised, the fabric turned following the direction of the corner, and the foot lowered for stitching to continue.

Placket An opening in a garment that provides support for fasteners, such as buttons, snaps, or zippers.

Plain weave The simplest of all the weaves; the weft yarn passes under one warp yarn, then over another one.

Pleat An even fold or series of folds in fabric, often partially stitched down. Commonly found in skirts to shape the waistline, but also in soft furnishings for decoration.

Pocket flap A piece of fabric that folds down to cover the opening of a pocket.

Polyester Manmade fiber that does not crease.

Presser foot The part of a sewing machine that is lowered on to the fabric to hold it in place over the needle plate while stitching. There are different feet available.

Pressing cloth Muslin or organza cloth placed over fabric to prevent marking or scorching when pressing.

Prick stitch Small spaced hand stitch with large spaces between each stitch. Often used to highlight the edge of a completed garment.

Raw edge Cut edge of fabric that requires finishing, for example using zigzag stitch, to prevent fraying.

Rayon Also known as viscose, rayon is often blended with other fibers.

Rever The turned-back front edge of a jacket or blouse to which the collar is attached.

Reverse stitch Machine stitch that simply stitches back over a row of stitches to secure the threads.

Right side The outer side of a fabric, or the visible part of a garment.

Rotary cutter Tool for cutting fabric neatly and easily, and useful for cutting multiple straight edges. It has different sizes of retractable blade.

Rouleau loop Button loop made from a strip of bias binding. It is used with a round ball-type button.

Round-end buttonhole stitch Machine stitch characterized by one end of the buttonhole being square and the other being round, to allow for the button shank.

Ruching Several lines of stitching worked to form a gathered area.

Ruffle Decorative gathered trim made from one or two layers of fabric.

Run and fell seam Also known as a flat fell seam, this seam is made on the right side of a garment and is very strong. It uses two lines of stitching and conceals all the raw edges, reducing fraying.

Running stitch A simple, evenly spaced straight stitch separated by equal-sized spaces, used for seaming and gathering.

Satin A fabric with a satin weave.

Satin weave A weave with a sheen, where the weft goes under four warp yarns, then over one.

Seam Stitched line where two edges of fabric are joined together.

Seam allowance The amount of fabric allowed for on a pattern where sections are to be joined together by a seam; usually this is $\frac{5}{8}$ in (1.5 cm).

Seam edge The cut edge of a seam allowance.

Seamline Line on paper pattern designated for stitching a seam; usually $\frac{5}{8}$ in (1.5 cm) from the seam edge.

Seam ripper A small, hooked tool used for undoing seams and unpicking stitches.

Seam roll Tubular pressing aid for pressing seams open on fabrics that mark.

Seersucker Woven cotton with a bubbly appearance due to stripes of puckers.

Self-bound seam Similar to the run and fell seam, except that it is stitched on the wrong side of the fabric.

Self-healing mat See **Cutting mat**.

Selvage Finished edge on a woven fabric. This runs parallel to the warp (lengthwise) threads.

Serger Machine used for quick stitching, trimming, and edging of fabric in a single action; it gives a professional finish to a garment. There are a variety of accessories that can be attached to a serger, which enable it to perform a greater range of functions.

Serger stitch A machine stitch that neatens edges and prevents fraying. It can be used on all types of fabric.

Sewing gauge Measuring tool with adjustable slider for checking small measurements, such as hem depths and seam allowances.

Sharps General purpose needle used for hand sewing.

Shell tuck Decorative fold of fabric stitched in place with a scalloped edge. *See also* Tuck.

Shirring Multiple rows of gathers sewn by machine. Often worked with shirring elastic in the bobbin to allow for stretch.

Shirting Closely woven, fine cotton with colored warp and weft yarns.

Silk Threads spun by the silkworm and used to create cool, luxurious fabrics.

Slip hem stitch Similar to herringbone stitch but is worked from right to left. Used mainly for hems.

Slotted seam A decorative seam where the edges of the seam open to reveal an under layer, which can be in a contrasting fabric.

Smocking Traditional way of gathering fabric using multiple rows of parallel gathers, stitched by hand, to produce fine tubes in the fabric.

Smocking dots Heat-transfer dots that can be transferred to fabric to be used as a guide for hand gathers.

Snaps Also known as press studs, these fasteners are used as a lightweight hidden fastener.

Snips Spring-loaded cutting tool used for cutting off thread ends.

Spandex Lightweight, soft, stretchable fiber.

Staple fibers These include both natural and manufactured fibers such as cotton, wool, flax, and polyester. They are short in length, and relatively narrow in thickness.

Stay stitch Straight machine stitch worked just inside a seam allowance to strengthen it and prevent it from stretching or breaking.

Stay tape Tape sewn to a specific area of an item for reinforcement, for example to help strengthen a seam.

Stem stitch An embroidery stitch frequently used to outline other stitched decoration.

Stitch in the ditch A line of straight stitches sewn on the right side of the work, in the ditch created by a seam. Used to secure waistbands and facings.

Stitch ripper *See* Seam ripper.

Straight stitch Plain machine stitch, used for most applications. The length of the stitch can be changed to suit the fabric.

Stretch stitch Machine stitch used for stretch knits and to help control difficult fabrics. It is worked with two stitches forward and one backward so that each stitch is worked three times.

Taffeta Smooth plain-weave fabric with a crisp appearance.

Tailor's buttonhole A buttonhole with one square end and one keyhole-shaped end, used on jackets and coats.

Tailor's chalk Square or triangular shaped piece of chalk used to mark fabric. Available in a variety of colors, tailor's chalk can be removed easily by brushing.

Tailor's ham A ham-shaped pressing cushion that is used to press shaped areas of garments.

Tailor's tacks Loose thread markings used to transfer symbols from a pattern to fabric.

Tape maker Tool for evenly folding the edges of a fabric strip, which can then be pressed to make binding.

Tape measure Flexible form of ruler made from plastic or fabric.

Tartan Fabric made using a twill weave from worsted yarns. Traditionally used for kilts.

Terry cloth Cotton fabric with loops on the surface.

Thimble Metal or plastic cap that fits over the top of a finger to protect it when hand sewing.

Toile A test or dry run of a paper pattern using calico. The toile helps you analyze the fit of the garment.

Top-stitch Machine straight stitching worked on the right side of an item, close to the finished edge, for decorative effect. Sometimes stitched in a contrasting color.

Top-stitched seam A seam finished with a row of top-stitching for decorative effect. This seam is often used on crafts and soft furnishings as well as garments.

Trace basting A method of marking fold and placement lines on fabric. Loose stitches are sewn along the lines on the pattern to the fabric beneath, then the thread loops are cut and the pattern removed.

Tracing wheel Tool used along with dressmaker's carbon paper to transfer pattern markings on to fabric.

Tuck Fold or pleat in fabric that is sewn in place, normally on the straight grain of the fabric. Often used to provide a decorative addition to a garment.

Tweed Traditional tweed is a rough fabric with a distinctive warp and weft. New tweed is a mix of chunky wool yarns, often in bright colors.

Twill weave Diagonal patterned weave.

Underlay Strip of fabric placed under the main fabric to strengthen it, for example under a pleat or buttonhole.

Understitch Machine straight stitching through facing and seam allowances that is invisible from the right side; this helps the facing to lie flat.

Velcro™ Two-part fabric fastening consisting of two layers, a "hook" side and a "loop" side; when pressed together the two pieces stick to each other.

Velvet Luxurious pile-weave fabric.

Venetian Luxurious wool with a satin weave.

Waistband Band of fabric attached to the waist edge of a garment to provide a neat finish.

Warp Lengthwise threads or yarns of a woven fabric.

Warp knit Made on a knitting machine, this knit is formed in a vertical and diagonal direction.

Weft Threads or yarns that cross the warp of a woven fabric.

Weft knit Made in the same way as hand knitting, this uses one yarn that runs horizontally.

Welt Strip of fabric used to make the edges of a pocket. *See also* Jetted pocket.

Whip stitch Diagonal hand stitch sewn along a raw edge to prevent fraying.

Wool A natural animal fiber available in a range of weights, weaves, and textures. It is comfortable to wear, crease-resistant, and ideal for tailoring.

Wool worsted A light, strong cloth made from good quality fibers.

Wrong side Reverse side of a fabric, the inside of a garment or other item.

Yoke The top section of a dress or skirt from which the rest of the garment hangs.

Zigzag stitch Machine stitch used to neaten and secure seam edges and for decorative purposes. The width and length of the zigzag can be altered.

Zipper Fastening widely used on garments consisting of two strips of fabric tape, carrying specially shaped metal or plastic teeth that lock together by means of a pull or slider. Zippers are available in different colors and weights.

Zipper foot Narrow machine foot with a single toe that can be positioned on either side of the needle.

INDEX

A

acetate 51
 acrylic fabrics 51
 all-in-one seam pockets 223
 alpaca interfacings 55
 altering patterns 62–73
 applied casings, waist edges 173
 appliqué 290
 mending tears with 300
 apron 324–7
 armhole facings 160–61
 arms, measuring 61
 arrowheads 91, 93
 awls 20

B

baby blanket 364–7
 baby towel 338–41
 back stitch 88, 90
 back waist, measuring 61
 bags
 drawstring bag 306–11
 shopping bag 334–7
 ball buttons 269
 banding
 hems with 240–43
 necklines in stretch knits 156
 bar bastes 89
 basting stitches 89
 batting
 quilting 291
 set-in sleeves 287
 beading foot 33
 beading needles 22
 beeswax 20
 belts 180–85
 belt carriers 181
 obi sashes 184–5, 363
 reinforced straight belts 182–3
 tie belts 184
 bent-handled shears 17
 betweens 22
 bias binding
 cased waist edges 173
 cuff openings 205
 cutting strips 147
 finishing waistband edges 177
 hems 230, 238
 neck edges 152–3
 sleeve hems 197
 tape makers 20
 bias fusible tape 277
 blanket, baby's 364–7
 blanket stitch 91

blind, Roman 346–9
 blind hem foot 32
 blind hem stitch 90, 93, 232
 blind tucks 111
 blouses
 collar with revers 166
 see also sleeves
 bobbins, sewing machine 32
 bodices
 altering patterns 62
 boned bodices 288–9
 joining skirts to 171
 lining 279
 bodkins 22
 body measurements 60–61
 bolster pillow 368–71
 boning 27
 boned bodices 288–9
 book cover 312–15
 bound buttonholes 266–7
 bound neck edges 152–3
 bound openings, cuffs 205
 bows 293
 box pleats 116–20
 braids 27
 horsehair braid hems 239
 bridal pins 23
 broderie anglaise 43
 buckles 183
 bust
 altering patterns 65–6
 darts 65
 measuring 60
 button loops 262, 268–9
 buttonhole chisels 15, 16
 buttonhole foot 32
 buttonhole stitch 91, 93
 buttonholes 262–7
 bound buttonholes 266–7
 in-seam buttonholes 267
 machine-made 264
 piped 265
 positioning 263
 repairing 299
 buttons 26
 ball buttons 269
 covered buttons 261
 repairing fabric under 299
 sewing on 258–60

C

café curtain 380–83
 calico 43
 toiles 74–5
 canvas interfacings 55

carbon paper 19
 cashmere 40
 casings
 sleeve edges 198
 waist edges 172–5
 centered zippers 253
 chalk
 chalk pencils 19
 tailor's chalk 19
 challis 40
 chambray 43
 checks, cutting out fabrics 80–81
 chenille needles 22
 chest, measuring 60
 chiffon 47
 child's skirt 320–23
 chintz 43
 circular ruffles 140–41
 clappers 29
 clean finish
 hems 230
 seam neatening 95
 clipping lines 82
 coats
 speed tailoring 282–7
 see also sleeves
 collar canvas 55
 collar point turners 21
 collars 160–67
 blouse collar with revers 166
 flat collars 161–3
 shawl collars 165
 speed tailoring 283, 286
 stand collars 164
 two-piece shirt collars 166–7
 computerized quilting 291
 concealed zipper foot 33
 contour darts 108
 cord
 corded gathers 128
 corded loops 268
 corded seams 98
 corded shirring 131
 corded tucks 113
 frog fastenings 269
 machine-corded buttonholes 264
 piped buttonholes 265
 cording foot 34
 corduroy 44
 corners
 hems with banding 240–43
 mitered corners 235
 patch pockets 216
 stitching 100–101
 stitching ruffles around 137
 cotton and linen mix fabrics 50

cotton fabrics 43–6
 cotton thread 24
 couture boned bodices 288–9
 covered buttons 261
 crepe 40
 crepe de chine 47
 crewel needles 22
 crinkle cotton 44
 cross stitch 91
 cross tucks 113
 crotch depth
 altering patterns 72, 73
 measuring 61
 cuffs 202–9
 attaching 208–9
 bound openings 205
 faced openings 204
 one-piece cuffs 203
 shirt sleeve plackets 206–7
 two-piece cuffs 203
 curtains
 café curtain 380–83
 hems 234–5
 interlining 294–5
 mitered corners 235
 pleats 124–5
 tie-backs 186–7
 weighting 235
 curved hems 229, 231
 curved seams
 reducing bulk 102–3
 stitching 101
 cushions
 project 316–19
 smocking 133
 cutting mats 16
 cutting out 76–83
 cutting shears 15, 16, 17
 cutting tools 16–17

D

damask 44
 darners 22
 darning foot 32
 darning holes 298
 darts
 altering patterns 64
 bust darts 65
 contour darts 108
 darted tucks 113
 French darts 65, 109
 plain darts 107
 pressing 109
 shaping to fit 107
 decorations 27

decorative faced hems 237
 decorative stitches, machines 93
 decorative zippers 257
 denim 44
 designs
 appliqué 290
 nap and 76
 diagonal stitch, reinforcing corners 216
 diagonal tacks 89
 diamond quilting 291
 difficult fabrics
 hems 233
 seams 99
 dolman sleeves 195
 door hanging 342–5
 dots, marking 82
 double banding, necklines in stretch knits 156
 double bias-bound hems 238
 double-bias bound neck edges 153
 double circular ruffles 141
 double cuffs 209
 double frills, attaching to edges 139
 double piping, edges 245
 double-pointed darts 108
 double ruffles 136
 double stitch 88
 double turn hems 232
 drafting rulers 19
 drawstring bag 306–11
 dress net, interlinings 276
 dress-weight linen 50
 dresses
 altering patterns 63, 67–9
 boned bodices 288–9
 joining skirts to 170
 dressing gown, kimono 358–63
 dressmaker's dummies 18
 marking hemlines 229
 dressmaker's pins 23
 drill 45
 duchesse satin 47
 dummies *see* dressmaker's dummies
 dupion 47, 48

E

edge-stitching, pleats 118
 edges
 double frills 139
 facings 146–7
 joining gathered edges 129
 sleeves 196–201
 stitching ruffles to 138–9
 trims 244–7
 see also hems
 elastic 27

repairing or replacing 303
 sleeve edges 198–9
 thread 24
 waistlines 174
 embroidery
 appliqué 290
 quilting 291
 embroidery foot 32
 embroidery machines 36–7
 embroidery scissors 15, 17
 embroidery thread 25
 emergency sewing kits 20
 envelopes, pattern 58
 equipment 12–37
 extra fine pins 23
 eyelets 273
 belts 183
 eyes
 hand-worked eyes 271
 hooks and eyes 26, 271

F

fabrics 38–55
 construction 53
 cotton 43–6
 cutting out 76–83
 grain and nap 76
 hems on difficult fabrics 233
 interfacings 54–5
 linen 50
 pattern layouts 78–81
 preparation 77
 reducing seam bulk 102–3
 seams on difficult fabrics 99
 silk 47–9
 wool 40–42
 facings 144–57
 armholes 160–61
 cased waist edges 173
 construction 145
 cuffs 204
 faced hems 236–7
 flat collars 163
 fly-front zips 254
 grown-on facing 152
 interfacings 145
 neatening edges 146–7
 neck facings 148–9, 151–4
 necklines in stretch knits 156–7
 notched collars 286
 plackets 155
 sleeve edges 201
 speed tailoring 283
 waistlines 176–7, 179
 fasteners 26, 270–73

buttons and buttonholes 26, 258–69
 eyelets 273
 hooks and eyes 26, 271
 snaps 272
 tape fasteners 272–3
 zippers 14, 250–57
 feet
 sewing machines 32
 sergers 34
 figure shapes 59
 fitted dresses
 altering patterns 63, 67–9
 joining skirts to 170
 flannel 41
 flaps, pocket 218–21
 flat collars 161–3
 flat fell stitch 90
 flat sleeves 193
 flat trims, on edges 244
 fleece hat and scarf 376–9
 flexible rulers 18
 flowerhead pins 23
 fly-front zippers 254
 folds, cutting out fabrics 79
 4-thread overlock stitch 93
 14-in-1 measure 21
 frame fusing, interfacings 277
 free embroidery foot 32
 freeform quilting 291
 French chalk 19
 French darts 65, 109
 French seams 96
 frills *see* ruffles
 fringes 27
 frog fastenings 269
 front hip pockets 224
 fur fabric 52
 seams 99
 fused hems 237
 fusible interfacings 54, 277
 speed tailoring 282–3
 fusible patches, mending tears
 300–301
 fusible tape 277

G

gabardine 41
 gathering foot 34
 gathers 126–33
 gathered piping edges 245
 joining skirts to bodices 171
 shirring 130–1
 smocking 132–3
 georgette 48
 gingham 45
 glass-headed pins 23
 glue pens 20
 goblet pleats, curtains 125

godets 122–3
 gored skirts, altering patterns 66,
 67, 69
 grain, fabrics 76
 gridded rulers 18
 grown-on facing 152
 grown-on waistbands 175
 gussets
 dolman sleeves 195
 paper bag pockets 217

H

haberdashery items 14, 26–7
 habutai 48
 hand sewing, stitches 88–91
 hat, polar fleece 376–8
 headings
 elasticated sleeve edges
 198
 ruffles with 135
 height, measuring 60
 hem stitch 90, 93
 hems 226–47
 altering patterns 64
 bias-bound hems 238
 curtains 234–5
 curved hems 229, 231
 on difficult fabrics 233
 faced hems 236–7
 fused hems 237
 hand-stitched hems 230–31,
 234
 horsehair braid hems 239
 interfaced hems 239
 linings 278
 machined hems 232–4
 marking a hemline 229
 pleats 120
 rolled hems 233
 sleeves 197
 speed tailoring 287
 on stretch knits 236
 turning up 229
 with banding 240–43
 see also edges
 herringbone stitch 90
 herringbone weave 53
 hip pockets 224
 hips
 altering patterns 68–9, 73
 measuring 61
 holes, darning 298
 hollow back, altering patterns 69
 Hong Kong finish 95
 hooks and eyes 26, 271
 hook and eye tape 273
 horizontal buttonholes 263
 horizontal quilting 291

horsehair braid hems 239
 household pins 23

I

in-seam buttonholes 267
 in-seam pockets 222–3
 inside leg, measuring 61
 interfacings 54–5, 276–7
 applying to facings 145
 hems 239
 speed tailoring 282–3
 interlinings 276, 277
 curtains 294–5
 inverted pleats 116, 118–20
 invisible zippers 251, 255
 ironing boards 29
 irons 28

J

jackets
 jettied pockets 284–5
 speed tailoring 282–7
 see also sleeves
 jersey 45
 jettied pockets 284–5
 with a flap 220–21
 jewelry roll 372–5

K

kangaroo pockets 225
 keyhole buttonhole stitch 93
 keyhole buttonholes 264
 kick pleats 118
 kimono 358–63
 kimono sleeves 194–5
 knife pleats 115, 116, 119,
 120
 knit fabrics 53
 cutting out 77
 darning holes 298
 grain 76
 hems 236
 necklines 156–7
 knitted interfacings 54
 knots, tying 88

L

lace pins 23
 lace trims, on edges 246
 lapped cuffs 208
 lapped seams 98
 lapped zippers 252
 layered buttons 260
 layouts, patterns 78–81
 leather 51

synthetic 52
 legs, measuring 61
 lengthening patterns 62–4
 linen fabrics 50
 lines, clipping 82
 linings 278–9
 interlining curtains 294–5
 interlinings 276, 277
 patch pockets 214–15
 speed tailoring 287
 liquid sealant 20
 locking stitch 88, 92
 long and short bastes 18
 loop turners 20
 loops, button 268–9

M

machine appliqué 290
 machine-corded buttonholes 264
 machine-made buttonholes 264–5
 machine shirring 130
 machined hems 232–4
 machines
 accessories 32–3
 buttonholes 264–5
 embroidery machines 36–7
 hems 232–4
 needles 32
 sergers 34–5
 sewing machines 30–33
 stitches 92–3
 madras 45
 manmade fabrics 51–2
 man's tie 350–53
 markers 83
 marking
 aids 19
 hemlines 229
 pattern symbols on fabric 82–3
 markings, pattern 59
 matka 48
 mats, place 354–7
 measurements, body 60–61
 measuring tools 18, 21
 mending 298–303
 metal bobbins 32
 metal tape measures 18
 metallic thread 25
 milliner's needles 22
 mini irons 28
 mitered corners 235
 mittens, pressing 29
 mock casings, waist edges 174–5
 mock French seams 97
 mohair 41
 multi-size patterns 59, 62

muslin 46
 interfacings 55
 interlinings 276

N

nap 76
 cutting out fabrics 79
 napkins 354–7
 neatening seams 94–5
 necklines
 bound edges 152–3
 facings 148–9, 151–4
 measuring 61
 piped edges 154
 stretch knits 156–7
 needles 15, 22
 needle case 332–3
 needle threaders 22
 overlockers 34
 sewing machines 32
 threading 88
 net interlinings 276
 non-fusible interfacings 55
 non-woven interfacings 54
 non-woven sew-in interfacings 55
 notched collars 286
 notches, marking 82
 nylon 51

O

obi sashes 184–5, 363
 one-piece cuffs 203
 one-way designs, nap and 76
 open-ended zips 251, 256
 organza 49
 interfacings 55
 interlinings 276
 outside leg, measuring 61
 overedge foot 32
 overedge stitch 93
 seam neatening 95
 oversized buttons 260

P

pants
 altering patterns 63, 72–3
 hooks and eyes 271
 waistlines 172–9
 zippers 251–7 paper, pattern 18
 paper bag pockets 217
 paper scissors 17
 parallel zigzag stitch, reinforcing corners 216
 patch method bound buttonholes 266–7
 patch pockets 213–16
 attaching 216
 kangaroo pockets 225

lined 214–15
 reinforcing corners 216
 self-lined 214
 square 215
 unlined 213
 pattern paper 18
 patterned fabrics, mending tears 302
 patterns 56–83
 altering 62–73
 layouts 78–81
 marking symbols onto fabric 82–3
 preparation 77
 reading 58–9
 symbols 59
 toiles 74–5
 pearl-headed pins 23
 pencil pleats, curtains 125
 pencils, chalk 19
 pens
 glue pens 20
 markers 83
 water/air-soluble pens 19
 Petersham-faced waistlines 177
 pile, nap and 76
 pillow, bolster 368–71
 pin cushions 15, 23, 333
 pin tuck foot 33
 pin tucks 111
 pinking shears 17
 hem finishes 231
 neatening facings 147
 seam neatening 94
 pins 14, 23
 unpicking stitches with 298
 piped buttonholes 265
 piped edges 244–5
 piped neck edges 154
 piped tucks 113
 piping foot 33
 place mats 354–7
 plackets 155
 shirt sleeves 206–7
 plain darts 107
 plain ruffles 135
 plain seams 94
 plain tucks 111
 plain weave 53
 plastic bobbins 32
 pleats 114–25
 adjusting to fit 121
 curtains 124–5
 edge-stitching 118
 godets 122–3
 hemming 120
 on the right side 115
 staying 119
 top-stitching 118
 on the wrong side 116
 with separate underlay 117

pliers 21
 pockets 212–25
 flaps 218–21
 front hip pockets 224
 in-seam pockets 222–3
 jettied pockets 220–21, 284–5
 kangaroo pockets 225
 paper bag pockets 217
 patch pockets 213–16
 welt pockets 219
 polar fleece hat and scarf 376–9
 polyester all-purpose thread 24
 polyester fabrics 52
 pressing darts 109
 pressing aids 28–9
 pressing cloths 29
 pressing mats 28
 pressing mittens 29
 prick stitch 90
 princess-line dresses, altering patterns 63, 67–9
 printed linens 50
 projects
 apron 324–7
 baby blanket 364–7
 baby towel 338–41
 bolster pillow 368–71
 book cover 312–15
 café curtain 380–83
 child's skirt 320–23
 cushion 316–19
 door hanging 342–5
 drawstring bag 306–11
 jewelry roll 372–5
 kimono 358–63
 man's tie 350–53
 place mat 354–7
 polar fleece hat and scarf 376–9
 Roman blind 346–9
 sewing aids 328–33
 shopping bag 334–7
 puff sleeves 192

Q

quilting 291
 quilting needles 22
 quilting pins 23

R

raglan sleeves 193
 rayon 52
 reading patterns 58–9
 reinforced buttons 260
 reinforced corners
 patch pockets 216
 stitching 101
 repairs 298–303
 retractable tape measures 18

revers, blouse collar with 166
 reverse stitch 92
 reinforcing corners 216
 ribbon-faced waistbands 179
 ribbon foot 33
 ribbons 27
 rolled hem foot 32
 rolled hems 233
 Roman blind 346–9
 roses 292
 rotary cutters 16
 rouleau loops 268
 round-end buttonhole stitch 93
 round-end buttonholes 264
 ruched tie-backs, curtains 187
 ruffles 134–41
 circular ruffles 140–41
 double ruffles 136, 139
 plain ruffles 135
 sleeve edges 200
 stitching around a corner 137
 stitching into a seam 137
 stitching to an edge 138–9
 with a heading 135
 rulers
 drafting rulers 19
 flexible rulers 18
 gridded rulers 18
 run and fell seams 96
 running stitch 90

S

safety pins 14, 23
 sashes, obi 184–5, 363
 satin 49
 duchesse satin 47
 satin weave 53
 scallops
 decorative faced hems 237
 shell tucks 112
 scarf, polar fleece 376–9
 scissors
 cutting out fabrics 82
 embroidery scissors 15, 17
 paper scissors 17
 scissor holder 330–31
 shears 15, 16
 trimming scissors 17
 unpicking stitches with 298
 sealant, liquid 20
 seam allowances, cased waist edges 174–5
 seam rippers 15, 16
 unpicking stitches 298
 seam rolls 29
 seams 94–101
 bust seams 66
 corners and curves 100–101
 on difficult fabrics 99
 godets 122
 in-seam buttonholes 267
 in-seam pockets 222–3
 inserting trimmings in 247
 joining two gathered edges 129
 marking for zipper placement 251
 mending splits 300
 neatening 94–5
 reducing bulk 102–3
 staying a gathered seam 129
 stitch finishes 103
 stitching ruffles into 137
 types of 96–8
 securing threads 88, 92
 seersucker 46
 self-bound seams 97
 self hems, sleeves 197
 self-threading needles 22
 serger stitch 93
 hems 230
 serger foot 34
 serger thread 25
 sergers 34–5
 finishing waistband edges 177
 gathers on 128
 neatening facings 147
 necklines in stretch knits 156
 rolled hems 233
 seams 94
 set-in sleeves 191, 287
 sew-in interfacings 276
 sewing aids 328–33
 sewing gauges 15, 18
 sewing machines *see* machines
 shanked buttons 260
 sharps 22
 shawl collars 165
 shears
 bent-handled shears 17
 cutting shears 15, 16, 17
 pinking shears 17
 sheer fabrics, seams 99
 shell tucks 112
 shirring 130–31
 shirting 46
 shirts
 cuffs 208–9
 sleeve plackets 206–7
 two-piece collars 166–7
 see also sleeves
 shopping bag 334–7
 shortening patterns 62–4
 shorts, altering patterns 63
 shoulder pads 287
 shoulders
 altering patterns 70
 measuring 61
 silk and wool mix fabrics 49
 silk fabrics 47–9

silk organza interlinings 276
 silk thread 24
 single bias-bound hems 238
 single piping, edges 244
 single-size patterns 59
 single turn hems 232
 skirts
 altering patterns 63, 66–9
 child's skirt 320–23
 lining 278–9
 striped or plaid fabrics 80
 waistlines 170–79
 zippers 251–7
 slashed necklines, facings 149
 sleeves 190–201
 altering patterns 62, 71
 cuffs 202–9
 edge finishes 196–201
 set-in sleeves 287
 speed tailoring 283, 287
 types of 190–95
 slip hem stitch 90
 slip bastes 89
 slotted fusible tape 277
 slotted seams 97
 smocking 132–3
 snap tape 273
 snaps 26, 272
 snips 16
 spaced tucks 111
 spandex 52
 speed tailoring 282–7
 spiral pins 23
 splits
 lining around 279
 mending in seams 300
 slashed necklines 149
 stand collars 164
 staples 23
 staying a gathered seam 129
 staying pleats 119
 stitch rippers 15, 16
 stitches 86–93
 finishes 103
 hand sewing 88–91
 hems 230–33
 machine stitches 92–3
 overlocker stitches 34
 securing threads 88, 92
 tacking stitches 89
 unpicking 298
 straight stitch 92
 straight-stitched rolled hems 233
 straw needles 22
 stretch knits *see* knit fabrics
 stretch stitch 93
 stripes
 cutting out fabrics 77, 80–81
 nap and 76

suede 51
 seams 99
 synthetic 52, 99
 suiting linen 50
 surface-mounted banding, hems 242–3
 symbols, on patterns 59, 82–3
 synthetic furs 52
 seams 99

T

tacks, tailor's 83
 taffeta 49
 tailoring, speed 282–7
 tailor's buttonholes 264
 tailor's chalk 19
 tailor's ham 29
 tailor's tacks 83
 tape makers 20
 tape measures 14, 18
 tapes
 fusible 277
 pleats on curtains 124
 tape fasteners 272–3
 tapestry needles 22
 tartan 41
 tears, mending 300–301
 terry cloth 46
 thimbles 14, 21
 thread chain tacks 89
 threading needles 88
 threads 14, 24–5
 pulling thread to obtain a straight edge 77
 securing 88
 3-step zigzag stitch 92
 3-thread overlock stitch 93
 seam neatening 95
 tie, man's 350–53
 tie-backs, curtain 186–7
 tie belts 184
 toiles 74–5
 tools 12–37
 top-stitching
 pleats 118
 seams 98, 103
 top-stitching thread 24
 towel, baby 338–41
 trace tracking 82
 tracing paper, pattern marking 83
 tracing wheels 19, 83
 trimming scissors 17
 trimmings 27
 on edges 244–7
 inserting in seams 247
 tucks 110–13
 tweed 42
 tweezers 20
 twill weave 53
 twin needle tucks 111

two-piece cuffs 203
 two-piece shirt collars 166–7
 tying knots 88

U

ultra glide foot 33
 understitching seams 103
 unpicking stitches 298

V

V necks, banding in stretch knits 157
 Velcro™ 26, 272
 velvet 46
 velvet mats 29
 venetian 42
 vertical buttonholes 263

W

waffle shirring 130
 waistlines 170–79
 altering patterns 66–8, 72
 attaching straight waistbands 178–9
 casings 172–5
 elastic 174
 facings 176–7, 179
 finishing edges 177
 joining skirts to bodices 171
 measuring 60
 repairing or replacing elastic 303
 ribbon-faced waistbands 179
 walking foot 33
 warp knit 53
 water/air-soluble pens 19
 wax 20
 weft knit 53
 weighting curtains 235
 welt pockets 219
 whip stitch 90
 wool fabrics 40–42
 worsted, wool 42
 woven fabrics, grain 76
 woven interfacings 54

Z

zigzag stitch 92
 hems 231
 mending tears 301
 neatening facings 147
 reinforcing corners 216
 rolled hems 233
 seam neatening 94
 zipper foot 33
 zippers 14, 250–57
 repairing 303
 shortening 251

About the Author

Alison Smith trained as an Art and Fashion Textile teacher, before becoming Head of Textiles at one of the largest schools in Birmingham, England, where she was able to pursue one of her key interests: the importance of teaching needlecrafts to boys, as well as girls. After successful spells as textiles tutor at the Liberty Sewing School, London, and the Janome Sewing School, Cheshire, Alison set up her own shop, Fabulous Fabric, and sewing school, Alison Victoria School of Sewing, in Ashby de la Zouch,

Leicestershire. Her school is the largest independent sewing school in England and offers courses and workshops on all aspects of dressmaking, tailoring, and corsetry.

Alison regularly lectures at specialist sewing shows, is a regular contributor to *Sewing World* magazine, and has made television appearances. She lives with her husband in Leicestershire, England, and has two grown-up children.

Acknowledgments

Author's acknowledgments

No book could ever be written without a little help. I would like to thank the following people for their help with the techniques and projects: Jackie Boddy, Nicola Corten, Ruth Cox, Helen Culver, Yvette Emmett, Averil Wing, and especially my husband, Nigel, for his continued encouragement and support, as well as my mother, Doreen Robbins, who is responsible for my learning to sew. The following companies have also provided invaluable help, by supplying the sewing machines, haberdashery, and fabrics: Janome UK Ltd, EQS, Linton, Adjustoform, Guttermann threads, The Button Company, YKK zips, Graham Smith Fabrics, Fabulous Fabric, Simplicity patterns, and Freudenberg Nonwovens LP.

Dorling Kindersley would like to thank:

Heather Haynes and Katie Hardwicke for editorial assistance; Elaine Hewson and Victoria Charles for design assistance; Susan Van Ha for photographic assistance; Hilary Bird for indexing; Elma Aquino; Alice Chadwick-Jones; and Beki Lamb. Special thanks from all at DK to Norma MacMillan for her exceptional professionalism and patience.

Picture Credits: Additional photography Laura Knox p76 tl, tr, 78 t, 80 t/2 and 4, 81b; Alamy images: D. Hurst, front jacket c. **Illustrator** Debajyoti Datta. **Patterns** John Hutchinson, pp 58-9, 62 b row, 63 t and c row, 65, 66, 67 t row, br, 68, 69 t row, bl, 70 tr, bc, br, 71, 72 tl, b row, 73, 81. **Additional artworks** Karen Cochrane p59 r.

Useful Websites

www.janome.com

Sewing machines, sergers, embroidery machines, software, and accessories.

www.schoolofsewing.co.uk

Alison Smith's sewing school and fabric shop. Offers courses and workshops on tailoring, dressmaking, and corsetry.

www.burdastyle.com

Sewing patterns, tutorials, and projects.

www.thesewingdictionary.com

A glossary of sewing terms and help navigating through various fabrics.

www.taunton.com/threads

Threads magazine: sewing patterns, advice, and features.

www.sewing.com

A global community where women learn and share about sewing.

www.sewing.org

Educational articles and projects.

www.simplicitynewlook.com

www.mccall.com

www.sewdirect.com

www.sewessentials.net

www.kwiksew.com

www.sewingpatterns.com

www.thesewingplace.com




Sewing patterns and supplies.

THE SEWING BOOK shows you **step-by-step** and in **sharp detail** all the techniques you'll ever need to sew absolutely anything. Every hand and machine stitch and technique is clearly shown and easy to follow, guiding you through all the moves you need to make.

Close-up photographs of hand and machine tools show you the best equipment for the job and guarantee you know exactly how to use it.

Stylish projects, for the home and to wear, enable you to hone your sewing skills to perfection.

Darts, tucks, pleats, hems, edges, pockets, buttonholes, zippers – whatever you're sewing, from home accessories to clothing, *The Sewing Book* shows you how.



Discover more at
www.dk.com